

Package ‘FuzzySTs’

July 13, 2026

Title Fuzzy Statistical Tools

Description The main goal of this package is to present various fuzzy statistical tools. It intends to provide an implementation of the theoretical and empirical approaches presented in the book entitled “The signed distance measure in fuzzy statistical analysis. Some theoretical, empirical and programming advances” <[doi:10.1007/978-3-030-76916-1](https://doi.org/10.1007/978-3-030-76916-1)>. For the theoretical approaches, see Berkachy R. and Donze L. (2019) <[doi:10.1007/978-3-030-03368-2_1](https://doi.org/10.1007/978-3-030-03368-2_1)>. For the empirical approaches, see Berkachy R. and Donze L. (2016) <ISBN: 978-989-758-201-1>. Important (non-exhaustive) implementation highlights of this package are as follows: (1) a numerical procedure to estimate the fuzzy difference and the fuzzy square. (2) two numerical methods of fuzzification. (3) a function performing different possibilities of distances, including the signed distance and the generalized signed distance for instance with all its properties. (4) numerical estimations of fuzzy statistical measures such as the variance, the moment, etc. (5) two methods of estimation of the bootstrap distribution of the likelihood ratio in the fuzzy context. (6) an estimation of a fuzzy confidence interval by the likelihood ratio method. (7) testing fuzzy hypotheses and/or fuzzy data by fuzzy confidence intervals in the Kwakernaak - Kruse and Meyer sense. (8) a general method to estimate the fuzzy p-value with fuzzy hypotheses and/or fuzzy data. (9) a method of estimation of global and individual evaluations of linguistic questionnaires. (10) numerical estimations of multi-ways analysis of variance models in the fuzzy context. The unbalance in the considered designs are also foreseen.

Version 0.5

Depends R (>= 3.0.0), FuzzyNumbers, polynom

License MIT + file LICENSE

Encoding UTF-8

Suggests knitr, rmarkdown

VignetteBuilder knitr

Config/roxygen2/version 8.0.0

NeedsCompilation no

Author Redina Berkachy [aut, cre] (ORCID:

<<https://orcid.org/0000-0002-7491-0416>>),

Laurent Donze [aut] (ORCID: <<https://orcid.org/0000-0003-3522-4672>>)

Maintainer Redina Berkachy <redina.berkachy@hefr.ch>

Repository CRAN

Date/Publication 2026-07-13 12:30:02 UTC

Contents

adjusted.weight.MI	4
adjusted.weight.SI	5
Bertoluzza	6
boot.mean.algo1	7
boot.mean.algo2	8
boot.mean.ml	9
cube	10
D2	11
Defuzz.FANOVA	11
Delta.pq	12
Delta_jki	13
distance	14
DSGD	15
DSGD.G	16
FANOVA	16
FANOVA.approximation	18
FANOVA.distance	19
FANOVA.exact	20
FANOVA.summary	21
fci.ml	22
fci.ml.boot	23
FMANOVA	24
FMANOVA.approximation	26
FMANOVA.distance	27
FMANOVA.exact	28
FMANOVA.interaction.summary	29
FMANOVA.summary	30
Ftests	30
FTukeyHSD	31
FUZZ	32
Fuzzy.CI.ML.test	33
Fuzzy.CI.test	35
Fuzzy.decisions	37
Fuzzy.decisions.ML	38
Fuzzy.Difference	40
Fuzzy.exact.variance	41
Fuzzy.exact.variance.poly.left	42
Fuzzy.exact.variance.poly.right	42
Fuzzy.p.value	43
Fuzzy.p.value.mean	44
fuzzy.predicted.values	46
fuzzy.residuals	47
Fuzzy.sample.mean	47
Fuzzy.sample.variance.approximation	48

Fuzzy.sample.variance.approximation1	48
Fuzzy.sample.variance.approximation2	49
Fuzzy.sample.variance.approximation3	49
Fuzzy.sample.variance.approximation4	50
Fuzzy.sample.variance.approximation5	50
Fuzzy.Square	51
Fuzzy.Square.poly.left	51
Fuzzy.Square.poly.right	52
Fuzzy.variance	53
GaussianBellFuzzyNumber	54
GaussianFuzzyNumber	55
GFUZZ	56
GLOB.EVAL	57
GLOB.EVAL.mean	59
GSGD	61
IND.EVAL	62
int.0	64
int.ct	65
int.simpson	65
int.t	66
integrate.num	66
is.alphacuts	67
is.balanced	67
is.fuzzification	68
is.trfuzzification	68
Kurtosis	69
Mid.Spr	70
Moment	71
nbreakpoints	72
n_jk..	73
n_jkq.	73
optimal.distance	74
p.value.fisher	75
p.value.log	77
p.value.mean.log	78
p.value.mean.normal	80
p.value.mean.poisson	81
p.value.mean.Student	82
p.value.normal	84
p.value.poisson	85
p.value.Student	87
prm_polygon	88
prm_trapezoid	91
prm_triangle	92
R	92
Rho1	93
Rho2	94
Rhop	94

Ri	95
Sample.variance	96
SEQ.ORDERING	97
SEQ.ORDERING.APPROXIMATION	97
SEQ.ORDERING.EXACT	98
SGD	98
Skewness	99
square	100
summary_prm	100
summary_prm_scores	101
tr.gfuzz	102
wabl	102
Weighted.fuzzy.mean	103
Index	105

<code>adjusted.weight.MI</code>	<i>Calculates the adjusted weight for a given main-item of a linguistic questionnaire</i>
---------------------------------	---

Description

Calculates the adjusted weight for a given main-item of a linguistic questionnaire

Usage

`adjusted.weight.MI(x, i, j, b_j, b_jk, SI)`

Arguments

- | | |
|-------------------|--|
| <code>x</code> | the data set to evaluate. |
| <code>i</code> | an observation index. |
| <code>j</code> | a main-item index. |
| <code>b_j</code> | an array referring to the initial weights given to each main-item of the considered main-item. This array will be afterwards re-calculated. |
| <code>b_jk</code> | a matrix of <code>length(b_j)</code> rows and <code>max(SI)</code> columns expressing the initial weights of each sub-item of a given main-item. |
| <code>SI</code> | an array representing the total numbers of sub-items per main-item. |

Value

A numerical value giving the readjusted weight of the main-item `j` for the observation `i`.

Examples

```

data <- matrix(c(3,4,2,3,3,2,4,3,3,4,3,4,4,2,5,3,4,4,3,3,3,4,4,3,
3,3,4,3,3,3,3,4,4,3,5,3,4,3,3,3), ncol = 4)
data <- as.data.frame(data)
MI <- 2
SI1 <- 2
SI2 <- 2
SI <- c(SI1,SI2)
b_j <- c(1/2,1/2)
b_jk <- matrix(c(0.5,0.5,0.5,0.5),nrow=2)
PA11 <- c(1,2,3,4,5)
PA12 <- c(1,2,3,4,5)
PA21 <- c(1,2,3,4,5)
PA22 <- c(1,2,3,4,5)
# -----
MF111 <- TrapezoidalFuzzyNumber(0,2,2,7)
MF112 <- TrapezoidalFuzzyNumber(2,7,7,15)
MF113 <- TrapezoidalFuzzyNumber(7,15,15,23)
MF114 <- TrapezoidalFuzzyNumber(15,23,23,28)
MF115 <- TrapezoidalFuzzyNumber(23,28,28,30)
MF11 <- GFUZZ(data, 1, 1, PA11, spec="Identical", breakpoints = 100)
# -----
MF121 <- TrapezoidalFuzzyNumber(0,2,2,7)
MF122 <- TrapezoidalFuzzyNumber(2,7,7,15)
MF123 <- TrapezoidalFuzzyNumber(7,15,15,23)
MF124 <- TrapezoidalFuzzyNumber(15,23,23,28)
MF125 <- TrapezoidalFuzzyNumber(23,28,28,30)
MF12 <- GFUZZ(data, 1, 2, PA12, spec="Identical", breakpoints = 100)
# -----
MF211 <- TrapezoidalFuzzyNumber(0,2,2,7)
MF212 <- TrapezoidalFuzzyNumber(2,7,7,15)
MF213 <- TrapezoidalFuzzyNumber(7,15,15,23)
MF214 <- TrapezoidalFuzzyNumber(15,23,23,28)
MF215 <- TrapezoidalFuzzyNumber(23,28,28,30)
MF21 <- GFUZZ(data, 2, 1, PA21, spec="Identical", breakpoints = 100)
# -----
MF221 <- TrapezoidalFuzzyNumber(0,2,2,7)
MF222 <- TrapezoidalFuzzyNumber(2,7,7,15)
MF223 <- TrapezoidalFuzzyNumber(7,15,15,23)
MF224 <- TrapezoidalFuzzyNumber(15,23,23,28)
MF225 <- TrapezoidalFuzzyNumber(23,28,28,30)
MF22 <- GFUZZ(data, 2, 2, PA22, spec="Identical", breakpoints = 100)
# -----
range <- matrix(c(0,0,0,0,28,28,28,28), ncol=2)
adjusted.weight.MI(data, 9, 1, b_j, b_jk, SI)

```

adjusted.weight.SI	<i>Calculates the adjusted weight for a given sub-item of a linguistic questionnaire</i>
--------------------	--

Description

Calculates the adjusted weight for a given sub-item of a linguistic questionnaire

Usage

```
adjusted.weight.SI(x, i, k, b_jk)
```

Arguments

x	the data set to evaluate.
i	an observation index.
k	a sub-item index.
b_jk	an array referring to the initial weights given to each sub-item of the considered main-item. This array will be afterwards re-calculated.

Value

A numerical value giving the readjusted weight of the sub-item k of the considered main-item for the observation i.

Examples

```
data <- matrix(c(3,4,2,3,3,2,4,3,3,4,3,4,4,2,5,3,4,4,3,3,3,4,4,3,
3,3,4,3,3,3,3,4,4,3,5,3,4,3,3,3), ncol = 4)
adjusted.weight.SI(data, 7, 1, c(0.5,0.5))
```

Bertoluzza

Calculates a distance by the $d_{Bertoluzza}$ between fuzzy numbers

Description

Calculates a distance by the $d_{Bertoluzza}$ between fuzzy numbers

Usage

```
Bertoluzza(X, Y, i = 1, j = 1, theta = 1/3, breakpoints = 100)
```

Arguments

X	a fuzzy number.
Y	a fuzzy number.
i	parameter of the density function of the Beta distribution, fixed by default to i = 1.
j	parameter of the density function of the Beta distribution, fixed by default to j = 1.

theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

boot.mean.algo1	<i>Estimates the bootstrap distribution of the likelihood ratio LR by the Algorithm 1 using the mean</i>
-----------------	--

Description

Estimates the bootstrap distribution of the likelihood ratio LR by the Algorithm 1 using the mean

Usage

```
boot.mean.algo1(
  data.fuzzified,
  distribution,
  sig,
  nsim = 100,
  mu = NA,
  sigma = NA,
  step = 0.1,
  margin = c(5, 5),
  breakpoints = 100,
  plot = TRUE
)
```

Arguments

data.fuzzified	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
distribution	a distribution chosen between "normal", "poisson", "Student" or "Logistic".
sig	a numerical value representing the significance level of the test.
nsim	an integer giving the number of replications needed in the bootstrap procedure. It is set to 100 by default.
mu	if the mean of the normal distribution is known, mu should be a numerical value. Otherwise, the argument mu is fixed to NA.
sigma	if the standard deviation of the normal distribution is known, sigma should be a numerical value. Otherwise, the argument sigma is fixed to NA.

step	a numerical value fixed to 0.1, defining the step of iterations on the interval [t-5; t+5].
margin	an optional numerical couple of values fixed to [5; 5], representing the range of calculations around the parameter t.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
plot	fixed by default to "FALSE". plot="FALSE" if a plot of the fuzzy number is not required.

Value

Returns a vector of decimals representing the bootstrap distribution of LR.

boot.mean.algo2	<i>Estimates the bootstrap distribution of the likelihood ratio LR by the Algorithm 2 using the mean</i>
-----------------	--

Description

Estimates the bootstrap distribution of the likelihood ratio LR by the Algorithm 2 using the mean

Usage

```
boot.mean.algo2(
  data.fuzzified,
  distribution,
  sig,
  nsim = 100,
  mu = NA,
  sigma = NA,
  step = 0.1,
  margin = c(5, 5),
  breakpoints = 100,
  plot = TRUE
)
```

Arguments

data.fuzzified	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
distribution	a distribution chosen between "normal", "poisson", "Student" or "Logistic".
sig	a numerical value representing the significance level of the test.
nsim	an integer giving the number of replications needed in the bootstrap procedure. It is set to 100 by default.
mu	if the mean of the normal distribution is known, mu should be a numerical value. Otherwise, the argument mu is fixed to NA.

sigma	if the standard deviation of the normal distribution is known, sigma should be a numerical value. Otherwise, the argument sigma is fixed to NA.
step	a numerical value fixed to 0.1, defining the step of iterations on the interval [t-5; t+5].
margin	an optional numerical couple of values fixed to [5; 5], representing the range of calculations around the parameter t.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
plot	fixed by default to "FALSE". plot="FALSE" if a plot of the fuzzy number is not required.

Value

Returns a vector of decimals representing the bootstrap distribution of LR.

boot.mean.ml	<i>Estimates the bootstrap distribution of the likelihood ratio LR by the Algorithm 1 or 2 using the mean</i>
--------------	---

Description

Estimates the bootstrap distribution of the likelihood ratio LR by the Algorithm 1 or 2 using the mean

Usage

```
boot.mean.ml(
  data.fuzzified,
  algorithm,
  distribution,
  sig,
  nsim = 100,
  mu = NA,
  sigma = NA,
  step = 0.1,
  margin = c(5, 5),
  breakpoints = 100,
  plot = TRUE
)
```

Arguments

data.fuzzified	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
algorithm	an algorithm chosen between "algo1" or "algo2".

distribution	a distribution chosen between "normal", "poisson", "Student" or "Logistic".
sig	a numerical value representing the significance level of the test.
nsim	an integer giving the number of replications needed in the bootstrap procedure. It is set to 100 by default.
mu	if the mean of the normal distribution is known, mu should be a numerical value. Otherwise, the argument mu is fixed to NA.
sigma	if the standard deviation of the normal distribution is known, sigma should be a numerical value. Otherwise, the argument sigma is fixed to NA.
step	a numerical value fixed to 0.1, defining the step of iterations on the interval [t-5; t+5].
margin	an optional numerical couple of values fixed to [5; 5], representing the range of calculations around the parameter t.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
plot	fixed by default to "FALSE". plot="FALSE" if a plot of the fuzzy number is not required.

Value

Returns a vector of decimals representing the bootstrap distribution of LR.

Examples

```
mat <- matrix(c(1,2,2,2,2,1),ncol=1)
MF111 <- TrapezoidalFuzzyNumber(0,1,1,2)
MF112 <- TrapezoidalFuzzyNumber(1,2,2,3)
PA11 <- c(1,2)
data.fuzzified <- FUZZ(mat,mi=1,si=1,PA=PA11)
emp.dist <- boot.mean.ml(data.fuzzified, algorithm = "algo1", distribution = "normal",
  sig = 0.05, nsim = 5, sigma = 1)
eta.boot <- quantile(emp.dist, probs = 95/100)
```

cube

Cube a number

Description

Cube a number

Usage

cube(x)

Arguments

x Number to be cubed

Value

The cube of the input

D2	<i>Calculates a distance by the D2 between fuzzy numbers</i>
----	--

Description

Calculates a distance by the D2 between fuzzy numbers

Usage

```
D2(X, Y, breakpoints = 100)
```

Arguments

X	a fuzzy number.
Y	a fuzzy number.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

Defuzz.FANOVA	<i>Defuzzify the fuzzy sums of squares calculated by a FANOVA model by an exact calculation or an approximation</i>
---------------	---

Description

Defuzzify the fuzzy sums of squares calculated by a FANOVA model by an exact calculation or an approximation

Usage

```
Defuzz.FANOVA(
  res,
  distance.type = "DSGD",
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

res	a result of a call of the function FANOVA, where method = "distance".
distance.type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
i	parameter of the density function of the Beta distribution, fixed by default to i = 1.
j	parameter of the density function of the Beta distribution, fixed by default to j = 1.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the Rho_p and Delta_pq. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq. By default, p is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

Returns a list of all the arguments of the function, the defuzzified total, treatment and residuals sums of squares, the decision made etc.

Delta.pq

Calculates a distance by the d_Delta.pq between fuzzy numbers

Description

Calculates a distance by the d_Delta.pq between fuzzy numbers

Usage

```
Delta.pq(X, Y, p, q, breakpoints = 100)
```

Arguments

X	a fuzzy number.
Y	a fuzzy number.
p	a positive integer such that $1 \leq p < \text{infinity}$, referring to the parameter of the Rho_p and Delta_pq.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

Delta_jki	<i>Calculates the factor Delta_jki</i>
-----------	--

Description

Calculates the factor Delta_jki

Usage

Delta_jki(x, i, K)

Arguments

x	a dataset.
i	an observation index.
K	the total number of linguistics in a sub-item.

Value

The response matrix of binary values (0 or 1) related to the answers of a particular dataset for its corresponding sub-items.

distance	<i>Calculates a distance between fuzzy numbers according to the chosen type</i>
----------	---

Description

Calculates a distance between fuzzy numbers according to the chosen type

Usage

```
distance(
  X,
  Y,
  type,
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

X	a fuzzy number.
Y	a fuzzy number.
type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
i	parameter of the density function of the Beta distribution, fixed by default to i = 1.
j	parameter of the density function of the Beta distribution, fixed by default to j = 1.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the Rho_p and Delta_pq.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

Examples

```
X <- TrapezoidalFuzzyNumber(1,2,3,4)
Y <- TrapezoidalFuzzyNumber(4,5,6,7)
distance(X, Y, type = "DSGD.G")
distance(X, Y, type = "GSGD")
```

DSGD

Calculates a distance by the SGD between fuzzy numbers

Description

Calculates a distance by the SGD between fuzzy numbers

Usage

```
DSGD(X, Y, i = 1, j = 1, breakpoints = 100, theta = 1/3)
```

Arguments

X	a fuzzy number.
Y	a fuzzy number.
i	parameter of the density function of the Beta distribution, fixed by default to i = 1.
j	parameter of the density function of the Beta distribution, fixed by default to j = 1.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.

Value

A numerical value.

DSGD.G	<i>Calculates a distance by the d_DSGD.G between fuzzy numbers</i>
--------	--

Description

Calculates a distance by the d_DSGD.G between fuzzy numbers

Usage

```
DSGD.G(X, Y, i = 1, j = 1, thetas = 1, breakpoints = 100)
```

Arguments

X	a fuzzy number.
Y	a fuzzy number.
i	parameter of the density function of the Beta distribution, fixed by default to i = 1.
j	parameter of the density function of the Beta distribution, fixed by default to j = 1.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

FANOVA	<i>Computes a FANOVA model by a convenient metric, an exact calculation or an approximation</i>
--------	---

Description

Computes a FANOVA model by a convenient metric, an exact calculation or an approximation

Usage

```

FANOVA(
  formula,
  dataset,
  data.fuzzified,
  sig,
  method,
  distance.type = "DSGD",
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100,
  int.method = "int.simpson",
  plot = TRUE
)

```

Arguments

<code>formula</code>	a description of the model to be fitted.
<code>dataset</code>	the data frame containing all the variables of the model.
<code>data.fuzzified</code>	the fuzzified data set constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix.
<code>sig</code>	a numerical value representing the significance level of the test.
<code>method</code>	the choices are the following: "distance", "exact", "approximation".
<code>distance.type</code>	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
<code>i</code>	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
<code>j</code>	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
<code>theta</code>	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: <code>d_Bertoluzza</code> , <code>d_mid/spr</code> and <code>d_phi-wabl/ldev/rdev</code> .
<code>thetas</code>	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the <code>d_theta star</code> and the <code>d_GSGD</code> distances.
<code>p</code>	a positive integer such that $1 \leq p < \text{infinity}$, referring to the parameter of the <code>Rho_p</code> and <code>Delta_pq</code> . By default, p is fixed to 2.
<code>q</code>	a decimal value between 0 and 1, referring to the parameter of the metric <code>Delta_pq</code> . By default, p is fixed to 0.5.

breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
int.method	the method of numerical integration. It is set by default to the Simpson method, i.e. int.method="int.simpson".
plot	fixed by default to "TRUE". plot="FALSE" if a plot of the fuzzy number is not required.

Value

Returns a list of all the arguments of the function, the total, treatment and residuals sums of squares, the coefficients of the model, the test statistics with the corresponding p-values, and the decision made.

Examples

```
mat <- matrix(c(1,1,1,1,1,1,1,2,2,2,2,3,2,3,4,2,3,3,2,4), ncol = 2)
data <- data.frame(mat)
data$X1 <- factor(data$X1)
MF121 <- TrapezoidalFuzzyNumber(0,1,1,2.2)
MF122 <- TrapezoidalFuzzyNumber(1.8,1.9,2.2,2.8)
MF123 <- TrapezoidalFuzzyNumber(1.9,2.3,3.1,3.3)
MF124 <- TrapezoidalFuzzyNumber(3.1,3.4,4.1,4.2)
PA12 <- c(1,2,3,4)
data.fuzzified <- GFUZZ(data, 1, 2, PA12, "Identical")
formula = X2 ~ X1
res <- FANOVA(formula, dataset = data, method = "distance", data.fuzzified = data.fuzzified,
sig = 0.05, distance.type = "wabl")
```

FANOVA.approximation *Computes a FANOVA model by an approximation*

Description

Computes a FANOVA model by an approximation

Usage

```
FANOVA.approximation(
  formula,
  dataset,
  data.fuzzified,
  sig,
  breakpoints = 100,
  int.method = "int.simpson",
  plot = TRUE
)
```

Arguments

formula	a description of the model to be fitted.
dataset	the data frame containing all the variables of the model.
data.fuzzified	the fuzzified data set constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix.
sig	a numerical value representing the significance level of the test.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
int.method	the method of numerical integration. It is set by default to the Simpson method, i.e. int.method="int.simpson".
plot	fixed by default to "TRUE". plot="FALSE" if a plot of the fuzzy number is not required.

Value

Returns a list of all the arguments of the function, the total, treatment and residuals sums of squares, the coefficients of the model, the test statistics with the corresponding p-values, and the decision made.

FANOVA.distance	<i>Computes a FANOVA model by a convenient metric</i>
-----------------	---

Description

Computes a FANOVA model by a convenient metric

Usage

```
FANOVA.distance(
  formula,
  dataset,
  data.fuzzified,
  sig,
  distance.type,
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

<code>formula</code>	a description of the model to be fitted.
<code>dataset</code>	the data frame containing all the variables of the model.
<code>data.fuzzified</code>	the fuzzified data set constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix.
<code>sig</code>	a numerical value representing the significance level of the test.
<code>distance.type</code>	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
<code>i</code>	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
<code>j</code>	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
<code>theta</code>	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to $1/3$ referring to the Lebesgue space. This measure is used in the calculations of the following distances: <code>d_Bertoluzza</code> , <code>d_mid/spr</code> and <code>d_phi-wabl/ldev/rdev</code> .
<code>thetas</code>	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the <code>d_theta star</code> and the <code>d_GSGD</code> distances.
<code>p</code>	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the <code>Rho_p</code> and <code>Delta_pq</code> . By default, <code>p</code> is fixed to 2.
<code>q</code>	a decimal value between 0 and 1, referring to the parameter of the metric <code>Delta_pq</code> . By default, <code>p</code> is fixed to 0.5.
<code>breakpoints</code>	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

Returns a list of all the arguments of the function, the total, treatment and residuals sums of squares, the coefficients of the model, the test statistics with the corresponding p-values, and the decision made.

FANOVA.exact

Computes a FANOVA model by an exact calculation

Description

Computes a FANOVA model by an exact calculation

Usage

```
FANOVA.exact(
  formula,
  dataset,
  data.fuzzified,
  sig,
  breakpoints = 100,
  int.method = "int.simpson",
  plot = TRUE
)
```

Arguments

formula	a description of the model to be fitted.
dataset	the data frame containing all the variables of the model.
data.fuzzified	the fuzzified data set constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix.
sig	a numerical value representing the significance level of the test.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
int.method	the method of numerical integration. It is set by default to the Simpson method, i.e. int.method="int.simpson".
plot	fixed by default to "TRUE". plot="FALSE" if a plot of the fuzzy number is not required.

Value

Returns a list of all the arguments of the function, the total, treatment and residuals sums of squares, the coefficients of the model, the test statistics with the corresponding p-values, and the decision made.

FANOVA.summary	<i>Prints the summary of the estimation of a FANOVA metric-based model</i>
----------------	--

Description

Prints the summary of the estimation of a FANOVA metric-based model

Usage

```
FANOVA.summary(res)
```

Arguments

res	a result of a call of the function FANOVA, where method = "distance".
-----	---

Value

Returns a list of summary statistics of the estimated model given in `res`, shown in a FANOVA table. In addition, the F-statistics with their p-values, and the decision are given.

fci.ml

Estimates a fuzzy confidence interval by the Likelihood method

Description

Estimates a fuzzy confidence interval by the Likelihood method

Usage

```
fci.ml(
  data.fuzzified,
  t,
  distribution,
  sig,
  mu = NA,
  sigma = NA,
  step = 0.05,
  margin = c(5, 5),
  breakpoints = 100,
  plot = TRUE
)
```

Arguments

<code>data.fuzzified</code>	a fuzzification matrix constructed by a call to the function <code>FUZZ</code> or the function <code>GFUZZ</code> , or a similar matrix. No NA are allowed.
<code>t</code>	a given numerical or fuzzy type parameter of the distribution.
<code>distribution</code>	a distribution chosen between "normal", "poisson", "Student" or "Logistic".
<code>sig</code>	a numerical value representing the significance level of the test.
<code>mu</code>	if the mean of the normal distribution is known, <code>mu</code> should be a numerical value. Otherwise, the argument <code>mu</code> is fixed to NA.
<code>sigma</code>	if the standard deviation of the normal distribution is known, <code>sigma</code> should be a numerical value. Otherwise, the argument <code>sigma</code> is fixed to NA.
<code>step</code>	a numerical value fixed to 0.05, defining the step of iterations on the interval $[t-5; t+5]$.
<code>margin</code>	an optional numerical couple of values fixed to $[5; 5]$, representing the range of calculations around the parameter <code>t</code> .
<code>breakpoints</code>	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
<code>plot</code>	fixed by default to "FALSE". <code>plot="FALSE"</code> if a plot of the fuzzy number is not required.

Value

Returns a matrix composed by 2 vectors representing the numerical left and right alpha-cuts. For this output, `is.alphacuts = TRUE`.

Examples

```
data <- matrix(c(1,2,3,2,2,1,1,3,1,2),ncol=1)
MF111 <- TrapezoidalFuzzyNumber(0,1,1,2)
MF112 <- TrapezoidalFuzzyNumber(1,2,2,3)
MF113 <- TrapezoidalFuzzyNumber(2,3,3,4)
PA11 <- c(1,2,3)
data.fuzzified <- FUZZ(data,mi=1,si=1,PA=PA11)
Fmean <- Fuzzy.sample.mean(data.fuzzified)
fci.ml(data.fuzzified, t = Fmean, distribution = "normal", sig= 0.05, sigma = 0.62)
```

fci.ml.boot

*Estimates a fuzzy confidence interval by the Likelihood method***Description**

Estimates a fuzzy confidence interval by the Likelihood method

Usage

```
fci.ml.boot(
  data.fuzzified,
  t,
  distribution,
  sig,
  coef.boot,
  mu = NA,
  sigma = NA,
  step = 0.05,
  margin = c(5, 5),
  breakpoints = 100,
  plot = TRUE
)
```

Arguments

<code>data.fuzzified</code>	a fuzzification matrix constructed by a call to the function <code>FUZZ</code> or the function <code>GFUZZ</code> , or a similar matrix. No NA are allowed.
<code>t</code>	a given numerical or fuzzy type parameter of the distribution.
<code>distribution</code>	a distribution chosen between "normal", "poisson", "Student" or "Logistic".
<code>sig</code>	a numerical value representing the significance level of the test.
<code>coef.boot</code>	a decimal representing the 1-sig-quantile of the bootstrap distribution of LR.

mu	if the mean of the normal distribution is known, mu should be a numerical value. Otherwise, the argument mu is fixed to NA.
sigma	if the standard deviation of the normal distribution is known, sigma should be a numerical value. Otherwise, the argument sigma is fixed to NA.
step	a numerical value fixed to 0.05, defining the step of iterations on the interval $[t-5; t+5]$.
margin	an optional numerical couple of values fixed to $[5; 5]$, representing the range of calculations around the parameter t.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
plot	fixed by default to "FALSE". plot="FALSE" if a plot of the fuzzy number is not required.

Value

Returns a matrix composed by 2 vectors representing the numerical left and right alpha-cuts. For this output, is.alphacuts = TRUE.

Examples

```
data <- matrix(c(1,2,3,2,2,1,1,3,1,2),ncol=1)
MF111 <- TrapezoidalFuzzyNumber(0,1,1,2)
MF112 <- TrapezoidalFuzzyNumber(1,2,2,3)
MF113 <- TrapezoidalFuzzyNumber(2,3,3,4)
PA11 <- c(1,2,3)
data.fuzzified <- FUZZ(data,mi=1,si=1,PA=PA11)
Fmean <- Fuzzy.sample.mean(data.fuzzified)
fci.ml.boot(data.fuzzified, t = Fmean, distribution = "normal", sig= 0.05, sigma = 0.62,
coef.boot = 1.8225)
```

FMANOVA

Computes a Multi-FANOVA model by a convenient metric, an exact calculation or an approximation

Description

Computes a Multi-FANOVA model by a convenient metric, an exact calculation or an approximation

Usage

```
FMANOVA(
  formula,
  dataset,
  data.fuzzified,
  sig = 0.05,
  method,
  distance.type = "DSGD",
```

```

index.var = NA,
i = 1,
j = 1,
theta = 1/3,
thetas = 1,
p = 2,
q = 0.5,
breakpoints = 100,
int.method = "int.simpson",
plot = TRUE
)

```

Arguments

formula	a description of the model to be fitted.
dataset	the data frame containing all the variables of the model.
data.fuzzified	the fuzzified data set constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix.
sig	a numerical value representing the significance level of the test.
method	the choices are the following: "distance", "exact", "approximation".
distance.type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
index.var	the column index of the considered variable for which the output will be printed. It is an argument of the Mult-FANOVA models by the exact and the approximation methods only.
i	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
j	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the Rho_p and Delta_pq. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq. By default, q is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
int.method	the method of numerical integration. It is set by default to the Simpson method, i.e. int.method="int.simpson".

plot fixed by default to "TRUE". plot="FALSE" if a plot of the fuzzy number is not required.

Value

Returns a list of all the arguments of the function, the total, treatment and residuals sums of squares, the coefficients of the model, the test statistics with the corresponding p-values, and the decision made.

Examples

```
mat <- matrix(c(2,2,1,1,2,2,2,2,2,2,2,2,2,2,1,1,1,1,2,3,4,4,3,1,2,5,4,4,3), ncol=3)
data <- data.frame(mat)
MF131 <- TrapezoidalFuzzyNumber(0,1,1,2)
MF132 <- TrapezoidalFuzzyNumber(1,2,2,3)
MF133 <- TrapezoidalFuzzyNumber(2,3,3,4)
MF134 <- TrapezoidalFuzzyNumber(3,4,4,5)
MF135 <- TrapezoidalFuzzyNumber(4,5,5,6)
PA13 <- c(1,2,3,4,5); mi <- 1; si <- 3
Yfuzz <- FUZZ(data,1,3,PA13)
attach(data)
formula <- X3 ~ X1 + X2
res <- FMANOVA(formula, data, Yfuzz, method = "distance", distance.type = "wabl")
detach(data)
```

FMANOVA.approximation *Computes a Mult-FANOVA model by an approximation*

Description

Computes a Mult-FANOVA model by an approximation

Usage

```
FMANOVA.approximation(
  formula,
  dataset,
  data.fuzzified,
  sig = 0.05,
  breakpoints = 100,
  index.var = NA,
  int.method = "int.simpson",
  plot = TRUE
)
```

Arguments

formula	a description of the model to be fitted.
dataset	the data frame containing all the variables of the model.
data.fuzzified	the fuzzified data set constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix.
sig	a numerical value representing the significance level of the test.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
index.var	the column index of the considered variable for which the output will be printed. It is an argument of the Mult-FANOVA models by the exact and the approximation methods only.
int.method	the method of numerical integration. It is set by default to the Simpson method, i.e. int.method="int.simpson".
plot	fixed by default to "TRUE". plot="FALSE" if a plot of the fuzzy number is not required.

Value

Returns a list of all the arguments of the function, the total, treatment and residuals sums of squares, the coefficients of the model, the test statistics with the corresponding p-values, and the decision made.

FMANOVA.distance	<i>Computes a Mult-FANOVA model by a convenient metric</i>
------------------	--

Description

Computes a Mult-FANOVA model by a convenient metric

Usage

```
FMANOVA.distance(
  formula,
  dataset,
  data.fuzzified,
  distance.type,
  sig = 0.05,
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

formula	a description of the model to be fitted.
dataset	the data frame containing all the variables of the model.
data.fuzzified	the fuzzified data set constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix.
distance.type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
sig	a numerical value representing the significance level of the test.
i	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
j	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to $1/3$ referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the Rho_p and Delta_pq. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq. By default, p is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

Returns a list of all the arguments of the function, the total, treatment and residuals sums of squares, the coefficients of the model, the test statistics with the corresponding p-values, and the decision made.

FMANOVA.exact

Computes a Mult-FANOVA model by an exact calculation

Description

Computes a Mult-FANOVA model by an exact calculation

Usage

```
FMANOVA.exact(
  formula,
  dataset,
  data.fuzzified,
  sig = 0.05,
  breakpoints = 100,
  int.method = "int.simpson",
  index.var = NA,
  plot = TRUE
)
```

Arguments

<code>formula</code>	a description of the model to be fitted.
<code>dataset</code>	the data frame containing all the variables of the model.
<code>data.fuzzified</code>	the fuzzified data set constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix.
<code>sig</code>	a numerical value representing the significance level of the test.
<code>breakpoints</code>	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
<code>int.method</code>	the method of numerical integration. It is set by default to the Simpson method, i.e. <code>int.method="int.simpson"</code> .
<code>index.var</code>	the column index of the considered variable for which the output will be printed. It is an argument of the Mult-FANOVA models by the exact and the approximation methods only.
<code>plot</code>	fixed by default to "TRUE". <code>plot="FALSE"</code> if a plot of the fuzzy number is not required.

Value

Returns a list of all the arguments of the function, the total, treatment and residuals sums of squares, the coefficients of the model, the test statistics with the corresponding p-values, and the decision made.

FMANOVA.interaction.summary

Prints the summary of the estimation of the interaction in a Mult-FANOVA metric-based model

Description

Prints the summary of the estimation of the interaction in a Mult-FANOVA metric-based model

Usage

```
FMANOVA.interaction.summary(res)
```

Arguments

`res` a result of a call of the function FMANOVA, where method = "distance".

Value

Returns a list of summary statistics of the estimated model given in `res`, shown in a FANOVA table. In addition, the F-statistics with their p-values, and the decision are given.

<code>FMANOVA.summary</code>	<i>Prints the summary of the estimation of a Mult-FANOVA metric-based model</i>
------------------------------	---

Description

Prints the summary of the estimation of a Mult-FANOVA metric-based model

Usage

```
FMANOVA.summary(res)
```

Arguments

`res` a result of a call of the function FMANOVA, where method = "distance".

Value

Returns a list of summary statistics of the estimated model given in `res`, shown in a FANOVA table. In addition, the F-statistics with their p-values, and the decision are given.

<code>Ftests</code>	<i>Calculates multiple tests corresponding to the fuzzy response variable</i>
---------------------	---

Description

Calculates multiple tests corresponding to the fuzzy response variable

Usage

```
Ftests(test)
```

Arguments

`test` a result of a call of the function FMANOVA.

Value

Returns a table of the following different indicators "Wilks", "F-Wilks", "Hotelling-Lawley trace" and "Pillai Trace".

Examples

```
mat <- matrix(c(2,2,1,1,2,2,2,2,2,2,2,2,2,2,1,1,1,1,2,3,4,4,3,1,2,5,4,4,3),ncol=3)
data <- data.frame(mat)
MF131 <- TrapezoidalFuzzyNumber(0,1,1,2)
MF132 <- TrapezoidalFuzzyNumber(1,2,2,3)
MF133 <- TrapezoidalFuzzyNumber(2,3,3,4)
MF134 <- TrapezoidalFuzzyNumber(3,4,4,5)
MF135 <- TrapezoidalFuzzyNumber(4,5,5,6)
PA13 <- c(1,2,3,4,5); mi <- 1; si <- 3
Yfuzz <- FUZZ(data,1,3,PA13)
attach(data)
formula <- X3 ~ X1 + X2
res <- FMANOVA(formula, data, Yfuzz, method = "distance", distance.type = "wabl")
Ftests(res)
detach(data)
```

FTukeyHSD	<i>Calculates the Tukey HSD test corresponding to the fuzzy response variable</i>
-----------	---

Description

Calculates the Tukey HSD test corresponding to the fuzzy response variable

Usage

```
FTukeyHSD(test, variable, cont = c(1, -1), conf.level = 0.95)
```

Arguments

test	a result of a call of the function FMANOVA.
variable	the name of a variable in the data set.
cont	the contrasts of the model. It is set by default to c(1,-1).
conf.level	the confidence level of the test. It is set by default to 0.95.

Value

Returns a table of comparisons of means of the different levels of a given factor, two by two. The table contains the means of populations, the lower and upper bounds of the confidence intervals, and their p-values.

Examples

```

mat <- matrix(c(2,2,1,1,2,2,2,2,2,2,2,2,2,2,1,1,1,1,2,3,4,4,3,1,2,5,4,4,3),ncol=3)
data <- data.frame(mat)
MF131 <- TrapezoidalFuzzyNumber(0,1,1,2)
MF132 <- TrapezoidalFuzzyNumber(1,2,2,3)
MF133 <- TrapezoidalFuzzyNumber(2,3,3,4)
MF134 <- TrapezoidalFuzzyNumber(3,4,4,5)
MF135 <- TrapezoidalFuzzyNumber(4,5,5,6)
PA13 <- c(1,2,3,4,5); mi <- 1; si <- 3
Yfuzz <- FUZZ(data,1,3,PA13)
attach(data)
formula <- X3 ~ X1 + X2
res <- FMANOVA(formula, data, Yfuzz, method = "distance", distance.type = "wabl")
FTukeyHSD(res, "X1")[[1]]
detach(data)

```

FUZZ	<i>Fuzzifies a variable modelled by trapezoidal or triangular fuzzy numbers</i>
------	---

Description

Fuzzifies a variable modelled by trapezoidal or triangular fuzzy numbers

Usage

```
FUZZ(data, mi, si, PA)
```

Arguments

data	a data set.
mi	the index of the main-item containing the concerned variable.
si	the index of the sub-item of a given main-item mi.
PA	a vector of the linguistic terms of the considered variable.

Value

A fuzzification matrix composed by 4 columns c(p,q,r,s), and m lines, i.e. number of observations.
No NA is allowed.

Examples

```

data <- matrix(c(1,2,3,2,2,1,1,3,1,2),ncol=1)
MF111 <- TrapezoidalFuzzyNumber(0,1,1,2)
MF112 <- TrapezoidalFuzzyNumber(1,2,2,3)
MF113 <- TrapezoidalFuzzyNumber(2,3,3,3)
PA11 <- c(1,2,3)
data.fuzzified <- FUZZ(data,mi=1,si=1,PA=PA11)
is.trfuzzification(data.fuzzified)

```

Fuzzy.CI.ML.test	<i>Computes a fuzzy inference test by the fuzzy confidence intervals method calculated by the Likelihood method</i>
------------------	---

Description

Computes a fuzzy inference test by the fuzzy confidence intervals method calculated by the Likelihood method

Usage

```
Fuzzy.CI.ML.test(
  data.fuzzified,
  H0,
  H1,
  t,
  mu = NA,
  sigma = NA,
  sig,
  distribution,
  coef.boot,
  distance.type = "DSGD",
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100,
  step = 0.05,
  margin = c(5, 5),
  plot = TRUE
)
```

Arguments

data.fuzzified	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
H0	a trapezoidal or a triangular fuzzy number representing the fuzzy null hypothesis.
H1	a trapezoidal or a triangular fuzzy number representing the fuzzy alternative hypothesis.
t	a given numerical or fuzzy type parameter of the distribution.
mu	if the mean of the normal distribution is known, mu should be a numerical value. Otherwise, the argument mu is fixed to NA.

<code>sigma</code>	if the standard deviation of the normal distribution is known, sigma should be a numerical value. Otherwise, the argument sigma is fixed to NA.
<code>sig</code>	a numerical value representing the significance level of the test.
<code>distribution</code>	a distribution chosen between "normal", "poisson", "Student" or "Logistic".
<code>coef.boot</code>	a decimal representing the 1-sig-quantile of the bootstrap distribution of LR.
<code>distance.type</code>	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
<code>i</code>	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
<code>j</code>	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
<code>theta</code>	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to $1/3$ referring to the Lebesgue space. This measure is used in the calculations of the following distances: <code>d_Bertoluzza</code> , <code>d_mid/spr</code> and <code>d_phi-wabl/ldev/rdev</code> .
<code>thetas</code>	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the <code>d_theta star</code> and the <code>d_GSGD</code> distances.
<code>p</code>	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the <code>Rho_p</code> and <code>Delta_pq</code> . By default, p is fixed to 2.
<code>q</code>	a decimal value between 0 and 1, referring to the parameter of the metric <code>Delta_pq</code> . By default, p is fixed to 0.5.
<code>breakpoints</code>	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
<code>step</code>	a numerical value fixed to 0.05, defining the step of iterations on the interval $[t-5; t+5]$.
<code>margin</code>	an optional numerical couple of values fixed to $[5; 5]$, representing the range of calculations around the parameter t.
<code>plot</code>	fixed by default to "FALSE". <code>plot="FALSE"</code> if a plot of the fuzzy number is not required.

Value

Returns a list composed by the arguments, the fuzzy confidence intervals, the fuzzy decisions, the defuzzified values and the decision made.

Examples

```
data <- matrix(c(1,2,3,2,2,1,1,3,1,2),ncol=1)
MF111 <- TrapezoidalFuzzyNumber(0,1,1,2)
MF112 <- TrapezoidalFuzzyNumber(1,2,2,3)
MF113 <- TrapezoidalFuzzyNumber(2,3,3,4)
PA11 <- c(1,2,3)
data.fuzzified <- FUZZ(data,mi=1,si=1,PA=PA11)
```

```

Fmean <- Fuzzy.sample.mean(data.fuzzified)
H0 <- TriangularFuzzyNumber(2.2,2.5,3)
H1 <- TriangularFuzzyNumber(2.5,2.5,5)
coef.boot <- 3.494829
(res <- Fuzzy.CI.ML.test(data.fuzzified, H0, H1, t = Fmean, sigma=0.7888,
coef.boot = coef.boot, sig=0.05, distribution="normal", distance.type="GSGD"))
res$decision

```

Fuzzy.CI.test	<i>Computes a fuzzy inference test by the traditional fuzzy confidence intervals</i>
---------------	--

Description

Computes a fuzzy inference test by the traditional fuzzy confidence intervals

Usage

```

Fuzzy.CI.test(
  type,
  H0,
  H1,
  t,
  s.d,
  n,
  sig,
  distribution,
  distance.type = "DSGD",
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100,
  plot = TRUE
)

```

Arguments

type	a category between "0", "1" and "2". The category "0" refers to a bilateral test, the category "1" for a lower unilateral one, and "2" for an upper unilateral test.
H0	a trapezoidal or a triangular fuzzy number representing the fuzzy null hypothesis.
H1	a trapezoidal or a triangular fuzzy number representing the fuzzy alternative hypothesis.
t	a given numerical or fuzzy type parameter of the distribution.

s.d	a numerical value for the standard deviation of the distribution.
n	the total number of observations of the data set.
sig	a numerical value representing the significance level of the test.
distribution	a distribution chosen between "normal", "poisson", "Student" or "Logistic".
distance.type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
i	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
j	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to $1/3$ referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the Rho_p and Delta_pq. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq. By default, p is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
plot	a logical rule "TRUE" or "FALSE" for defining whether to plot the corresponding graphs or not.

Value

Returns a list composed by the arguments, the fuzzy confidence intervals, the fuzzy decisions, the defuzzified values and the decision made.

Examples

```
H0 <- TriangularFuzzyNumber(2.9,3,3.1)
H1 <- TriangularFuzzyNumber(3,3,5)
res <- Fuzzy.CI.test(type = 0, H0, H1, t = TriangularFuzzyNumber(0.8,1.80,2.80), s.d = 0.79,
n = 10, sig = 0.05, distribution = "normal", distance.type="GSGD")
```

Fuzzy.decisions	<i>Computes the fuzzy decisions of a fuzzy inference test by the traditional fuzzy confidence intervals</i>
-----------------	---

Description

Computes the fuzzy decisions of a fuzzy inference test by the traditional fuzzy confidence intervals

Usage

```
Fuzzy.decisions(
  type,
  H0,
  H1,
  t,
  s.d,
  n,
  sig,
  distribution,
  distance.type = "DSGD",
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

type	a category between "0", "1" and "2". The category "0" refers to a bilateral test, the category "1" for a lower unilateral one, and "2" for an upper unilateral test.
H0	a trapezoidal or a triangular fuzzy number representing the fuzzy null hypothesis.
H1	a trapezoidal or a triangular fuzzy number representing the fuzzy alternative hypothesis.
t	a given numerical or fuzzy type parameter of the distribution.
s.d	a numerical value for the standard deviation of the distribution.
n	the total number of observations of the data set.
sig	a numerical value representing the significance level of the test.
distribution	a distribution chosen between "normal", "poisson", "Student" or "Logistic".
distance.type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".

i	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
j	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to $1/3$ referring to the Lebesgue space. This measure is used in the calculations of the following distances: $d_Bertoluzza$, d_mid/spr and $d_phi-wabl/ldev/rdev$.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \text{infinity}$, referring to the parameter of the Rho_p and $Delta_pq$. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric $Delta_pq$. By default, p is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

Returns a list composed by the arguments, the fuzzy confidence intervals and their complements, the fuzzy decisions and the defuzzified values.

Examples

```
H0 <- alphacut(TriangularFuzzyNumber(2.9,3,3.1), seq(0,1, 0.01))
H1 <- alphacut(TriangularFuzzyNumber(3,3,5), seq(0,1,0.01))
t <- alphacut(TriangularFuzzyNumber(0.8,1.80,2.80), seq(0,1,0.01))
res <- Fuzzy.decisions(type = 0, H0, H1, t = t, s.d = 0.79, n = 10, sig = 0.05,
distribution = "normal", distance.type = "GSGD")
```

Fuzzy.decisions.ML	<i>Computes the fuzzy decisions of a fuzzy inference test by the fuzzy confidence intervals by the likelihood method</i>
--------------------	--

Description

Computes the fuzzy decisions of a fuzzy inference test by the fuzzy confidence intervals by the likelihood method

Usage

```
Fuzzy.decisions.ML(
  data.fuzzified,
  H0,
  H1,
```

```

    t,
    coef.boot,
    mu = NA,
    sigma = NA,
    sig,
    distribution,
    distance.type = "DSGD",
    i = 1,
    j = 1,
    theta = 1/3,
    thetas = 1,
    p = 2,
    q = 0.5,
    breakpoints = 100,
    step = 0.05,
    margin = c(5, 5),
    plot = FALSE
)

```

Arguments

data.fuzzified	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
H0	a trapezoidal or a triangular fuzzy number representing the fuzzy null hypothesis.
H1	a trapezoidal or a triangular fuzzy number representing the fuzzy alternative hypothesis.
t	a given numerical or fuzzy type parameter of the distribution.
coef.boot	a decimal representing the 1-sig-quantile of the bootstrap distribution of LR.
mu	if the mean of the normal distribution is known, mu should be a numerical value. Otherwise, the argument mu is fixed to NA.
sigma	if the standard deviation of the normal distribution is known, sigma should be a numerical value. Otherwise, the argument sigma is fixed to NA.
sig	a numerical value representing the significance level of the test.
distribution	a distribution chosen between "normal", "poisson", "Student" or "Logistic".
distance.type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
i	parameter of the density function of the Beta distribution, fixed by default to i = 1.
j	parameter of the density function of the Beta distribution, fixed by default to j = 1.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.

thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \text{infinity}$, referring to the parameter of the Rho_p and Delta_pq. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq. By default, p is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
step	a numerical value fixed to 0.05, defining the step of iterations on the interval [t-5; t+5].
margin	an optional numerical couple of values fixed to [5; 5], representing the range of calculations around the parameter t.
plot	fixed by default to "FALSE". plot="FALSE" if a plot of the fuzzy number is not required.

Value

Returns a list composed by the arguments, the fuzzy confidence intervals, the fuzzy decisions, the defuzzified values and the decision made.

Examples

```
data <- matrix(c(1,2,3,2,2,1,1,3,1,2),ncol=1)
MF111 <- TrapezoidalFuzzyNumber(0,1,1,2)
MF112 <- TrapezoidalFuzzyNumber(1,2,2,3)
MF113 <- TrapezoidalFuzzyNumber(2,3,3,4)
PA11 <- c(1,2,3)
data.fuzzified <- FUZZ(data,mi=1,si=1,PA=PA11)
H0 <- alphacut(TriangularFuzzyNumber(2.9,3,3.1), seq(0,1, 0.01))
H1 <- alphacut(TriangularFuzzyNumber(3,3,5), seq(0,1,0.01))
t <- alphacut(TriangularFuzzyNumber(0.8,1.80,2.80), seq(0,1,0.01))
coef.boot <- 3.470085
res <- Fuzzy.decisions.ML(data.fuzzified, H0, H1, t = t, coef.boot = coef.boot,
sigma = 0.79, sig = 0.05, distribution = "normal", distance.type = "GSGD")
```

Fuzzy.Difference

Calculates the difference between two fuzzy numbers

Description

Calculates the difference between two fuzzy numbers

Usage

```
Fuzzy.Difference(X, Y, alphacuts = FALSE, breakpoints = 100)
```

Arguments

X	a fuzzy number of any type.
Y	a fuzzy number of any type.
alphacuts	fixed by default to "FALSE". No alpha-cuts are printed in this case.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

If the parameter alphacuts="TRUE", the function returns a matrix composed by 2 vectors representing the left and right alpha-cuts. For this output, is.alphacuts = TRUE. If the parameter alphacuts="FALSE", the function returns a trapezoidal fuzzy number given by the quadruple (p,q,r,s), such that $p \leq q \leq r \leq s$.

Examples

```
X <- TrapezoidalFuzzyNumber(5,6,7,8)
Y <- TrapezoidalFuzzyNumber(1,2,3,4)
Fuzzy.Difference(X,Y)
```

`Fuzzy.exact.variance` *Calculates the exact variance*

Description

Calculates the exact variance

Usage

```
Fuzzy.exact.variance(data.fuzzified, breakpoints = 100, plot = FALSE)
```

Arguments

data.fuzzified	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
plot	fixed by default to "FALSE". plot="TRUE" if a plot of the fuzzy number is required.

Value

The numerical alpha-cuts of the estimated fuzzy variance.

```
Fuzzy.exact.variance.poly.left
```

Gives the polynomial forms of the numerical alpha-cuts modelling the exact variance

Description

Gives the polynomial forms of the numerical alpha-cuts modelling the exact variance

Usage

```
Fuzzy.exact.variance.poly.left(data.fuzzified, breakpoints = 100)
```

Arguments

`data.fuzzified` a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.

`breakpoints` a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A table composed by the coefficients of the second order equations of the left side, given at the corresponding definitions domains.

```
Fuzzy.exact.variance.poly.right
```

Gives the polynomial forms of the numerical alpha-cuts modelling the exact variance

Description

Gives the polynomial forms of the numerical alpha-cuts modelling the exact variance

Usage

```
Fuzzy.exact.variance.poly.right(data.fuzzified, breakpoints = 100)
```

Arguments

`data.fuzzified` a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.

`breakpoints` a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A table composed by the coefficients of the second order equations of the right side, given at the corresponding definitions domains.

Fuzzy.p.value

Computes the fuzzy p-value of a given fuzzy hypothesis test

Description

Computes the fuzzy p-value of a given fuzzy hypothesis test

Usage

```
Fuzzy.p.value(
  type,
  H0,
  H1,
  t,
  s.d = 1,
  n,
  sig,
  distribution,
  distance.type = "DSGD",
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

type	a category between "0", "1" and "2". The category "0" refers to a bilateral test, the category "1" for a lower unilateral one, and "2" for an upper unilateral test.
H0	a trapezoidal or a triangular fuzzy number representing the fuzzy null hypothesis.
H1	a trapezoidal or a triangular fuzzy number representing the fuzzy alternative hypothesis.
t	a given numerical or fuzzy type parameter of the distribution.
s.d	a numerical value for the standard deviation of the distribution.
n	the total number of observations of the data set.
sig	a numerical value representing the significance level of the test.

distribution	a distribution chosen between "normal", "poisson", "Student" or "Logistic".
distance.type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
i	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
j	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to $1/3$ referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the Rho_p and Delta_pq. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq. By default, p is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

Returns the defuzzified p-value and the decision made.

Examples

```
H0 <- TriangularFuzzyNumber(2.2,2.5,3)
H1 <- TriangularFuzzyNumber(2.5,2.5,5)
Fuzzy.p.value(type=1, H0, H1, t=TriangularFuzzyNumber(0.8,1.8,2.8),
s.d=0.7888, n=10, sig=0.05, distribution="normal", distance.type="GSGD")
```

Fuzzy.p.value.mean	<i>Computes the fuzzy p-value of a given fuzzy hypothesis test for the mean</i>
--------------------	---

Description

Computes the fuzzy p-value of a given fuzzy hypothesis test for the mean

Usage

```
Fuzzy.p.value.mean(
  data.fuzzified,
  type,
  H0,
  H1,
  s.d = 1,
  sig,
  distribution,
  distance.type = "DSGD",
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

<code>data.fuzzified</code>	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
<code>type</code>	a category between "0", "1" and "2". The category "0" refers to a bilateral test, the category "1" for a lower unilateral one, and "2" for an upper unilateral test.
<code>H0</code>	a trapezoidal or a triangular fuzzy number representing the fuzzy null hypothesis.
<code>H1</code>	a trapezoidal or a triangular fuzzy number representing the fuzzy alternative hypothesis.
<code>s.d</code>	a numerical value for the standard deviation of the distribution.
<code>sig</code>	a numerical value representing the significance level of the test.
<code>distribution</code>	a distribution chosen between "normal", "poisson" or "Student".
<code>distance.type</code>	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
<code>i</code>	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
<code>j</code>	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
<code>theta</code>	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: <code>d_Bertoluzza</code> , <code>d_mid/spr</code> and <code>d_phi-wabl/ldev/rdev</code> .
<code>thetas</code>	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the <code>d_theta star</code> and the <code>d_GSGD</code> distances.

p	a positive integer such that $1 \leq p < \text{infinity}$, referring to the parameter of the Rho_p and Delta_pq. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq. By default, p is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

Returns the defuzzified p-value and the decision made.

Examples

```
data <- matrix(c(1,2,3,2,2,1,1,3,1,2),ncol=1)
MF111 <- TrapezoidalFuzzyNumber(0,1,1,2)
MF112 <- TrapezoidalFuzzyNumber(1,2,2,3)
MF113 <- TrapezoidalFuzzyNumber(2,3,3,4)
PA11 <- c(1,2,3)
data.fuzzified <- FUZZ(data,mi=1,si=1,PA=PA11)
H0 <- TriangularFuzzyNumber(2.2,2.5,3)
H1 <- TriangularFuzzyNumber(2.5,2.5,5)
Fuzzy.p.value.mean(data.fuzzified, type=1, H0, H1, s.d=0.7888, sig=0.05,
distribution="normal", distance.type="GSGD")
```

fuzzy.predicted.values

Calculates the fuzzy predicted values

Description

Calculates the fuzzy predicted values

Usage

```
fuzzy.predicted.values(dataset, coef.model)
```

Arguments

dataset	the data frame containing all the variables of the model.
coef.model	the coefficients of the model.

Value

Returns a matrix containing the alpha-cuts of the fuzzy predicted values.

fuzzy.residuals	<i>Calculates the fuzzy residuals</i>
-----------------	---------------------------------------

Description

Calculates the fuzzy residuals

Usage

```
fuzzy.residuals(data.fuzzified, predicted.values)
```

Arguments

`data.fuzzified` the fuzzified data set constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix.

`predicted.values` the fuzzy predicted values constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix.

Value

Returns a matrix containing the alpha-cuts of the fuzzy residuals.

Fuzzy.sample.mean	<i>Calculates the fuzzy sample mean</i>
-------------------	---

Description

Calculates the fuzzy sample mean

Usage

```
Fuzzy.sample.mean(data.fuzzified, breakpoints = 100, alphacuts = FALSE)
```

Arguments

`data.fuzzified` a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.

`breakpoints` a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

`alphacuts` fixed by default to "FALSE". No alpha-cuts are printed in this case.

Value

If the parameter `alphacuts="TRUE"`, the function returns a matrix composed by 2 vectors representing the numerical left and right alpha-cuts. For this output, `is.alphacuts = TRUE`. If the parameter `alphacuts="FALSE"`, the function returns a trapezoidal fuzzy number given by the quadruple (p,q,r,s).

Examples

```
mat <- matrix(c(1,2,2,3,3,4,4,5), ncol =4)
Fuzzy.sample.mean(mat)
```

```
Fuzzy.sample.variance.approximation
```

Fuzzy sample variance (approx) - general

Description

Fuzzy sample variance (approx) - general

Usage

```
Fuzzy.sample.variance.approximation(data.fuzzified, appro.id)
```

Arguments

`data.fuzzified` a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.

`appro.id` an integer between 1 and 5 giving the method of approximation chosen.

Value

A numerical value.

```
Fuzzy.sample.variance.approximation1
```

Fuzzy sample variance (approx) - method 1

Description

Fuzzy sample variance (approx) - method 1

Usage

```
Fuzzy.sample.variance.approximation1(data.fuzzified)
```

Arguments

`data.fuzzified` a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.

Value

A numerical value.

Fuzzy.sample.variance.approximation2

Fuzzy sample variance (approx) - method 2

Description

Fuzzy sample variance (approx) - method 2

Usage

Fuzzy.sample.variance.approximation2(data.fuzzified)

Arguments

`data.fuzzified` a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.

Value

A numerical value.

Fuzzy.sample.variance.approximation3

Fuzzy sample variance (approx) - method 3

Description

Fuzzy sample variance (approx) - method 3

Usage

Fuzzy.sample.variance.approximation3(data.fuzzified)

Arguments

`data.fuzzified` a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.

Value

A numerical value.

Fuzzy.sample.variance.approximation4

Fuzzy sample variance (approx) - method 4

Description

Fuzzy sample variance (approx) - method 4

Usage

Fuzzy.sample.variance.approximation4(data.fuzzified)

Arguments

data.fuzzified a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.

Value

A numerical value.

Fuzzy.sample.variance.approximation5

Fuzzy sample variance (approx) - method 5

Description

Fuzzy sample variance (approx) - method 5

Usage

Fuzzy.sample.variance.approximation5(data.fuzzified)

Arguments

data.fuzzified a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.

Value

A numerical value.

Fuzzy.Square	<i>Calculates numerically the square of a fuzzy number</i>
--------------	--

Description

Calculates numerically the square of a fuzzy number

Usage

```
Fuzzy.Square(F1L, breakpoints = 100, plot = FALSE)
```

Arguments

F1L	a fuzzy number.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
plot	fixed by default to "FALSE". plot="TRUE" if a plot of the fuzzy number is required.

Value

A matrix composed by 2 vectors representing the numerical left and right alpha-cuts. For this output, is.alphacuts = TRUE.

Examples

```
X <- TrapezoidalFuzzyNumber(1,2,3,4)
Fuzzy.Square(X, plot=TRUE)
```

Fuzzy.Square.poly.left

Gives the polynomial expression of the left alpha-levels of the numerical square of a fuzzy number

Description

Gives the polynomial expression of the left alpha-levels of the numerical square of a fuzzy number

Usage

```
Fuzzy.Square.poly.left(F1L, breakpoints = 100)
```

Arguments

F1L	a fuzzy number.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A table containing print the related polynoms at the corresponding definition domains.

Examples

```
X <- TrapezoidalFuzzyNumber(1,2,3,4)
Fuzzy.Square.poly.left(X)
```

```
Fuzzy.Square.poly.right
```

Gives the polynomial expression of the right alpha-levels of the numerical square of a fuzzy number

Description

Gives the polynomial expression of the right alpha-levels of the numerical square of a fuzzy number

Usage

```
Fuzzy.Square.poly.right(F1L, breakpoints = 100)
```

Arguments

F1L	a fuzzy number.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A table containing print the related polynoms at the corresponding definition domains.

Examples

```
X <- TrapezoidalFuzzyNumber(1,2,3,4)
Fuzzy.Square.poly.right(X)
```

Fuzzy.variance	<i>Calculates the variance by a chosen method: distance, exact or approximation</i>
----------------	---

Description

Calculates the variance by a chosen method: distance, exact or approximation

Usage

```
Fuzzy.variance(
  data.fuzzified,
  method,
  dist.type = "DSGD",
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100,
  int.method = "int.simpson",
  plot = FALSE
)
```

Arguments

<code>data.fuzzified</code>	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
<code>method</code>	choices are the following: "distance", "exact", "approximation1", "approximation2", "approximation3", "approximation4", "approximation5".
<code>dist.type</code>	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
<code>i</code>	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
<code>j</code>	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
<code>theta</code>	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: <code>d_Bertoluzza</code> , <code>d_mid/spr</code> and <code>d_phi-wabl/ldev/rdev</code> .
<code>thetas</code>	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the <code>d_theta star</code> and the <code>d_GSGD</code> distances.

p	a positive integer such that $1 \leq p < \text{infinity}$, referring to the parameter of the Rho_p and Delta_pq. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq. By default, q is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
int.method	the integration method could be one of the following four methods: "int.0", "int.t", "int.ct" and "int.simpson".
plot	fixed by default to "FALSE". plot="TRUE" if a plot of the fuzzy number is required.

Value

If the parameter method = "distance", returns a numerical value. If else, returns the numerical α -cuts of the estimated fuzzy variance.

Examples

```
data <- matrix(c(1,2,3,2,2,1,1,3,1,2),ncol=1)
MF111 <- TrapezoidalFuzzyNumber(0,1,1,2)
MF112 <- TrapezoidalFuzzyNumber(1,2,2,3)
MF113 <- TrapezoidalFuzzyNumber(2,3,3,3)
PA11 <- c(1,2,3)
data.fuzzified <- FUZZ(data,mi=1,si=1,PA=PA11)
Fuzzy.variance(data.fuzzified, method = "approximation5", plot=TRUE)
Fuzzy.variance(data.fuzzified, method = "distance")
```

GaussianBellFuzzyNumber

Creates a Gaussian two-sided bell fuzzy number

Description

Creates a Gaussian two-sided bell fuzzy number

Usage

```
GaussianBellFuzzyNumber(
  left.mean,
  left.sigma,
  right.mean,
  right.sigma,
  alphacuts = FALSE,
  margin = c(5, 5),
  step = 0.01,
  breakpoints = 100,
  precision = 4,
  plot = FALSE
)
```

Arguments

<code>left.mean</code>	a numerical value of the parameter μ of the left Gaussian curve.
<code>left.sigma</code>	a numerical value of the parameter σ of the left Gaussian curve.
<code>right.mean</code>	a numerical value of the parameter μ of the right Gaussian curve.
<code>right.sigma</code>	a numerical value of the parameter σ of the right Gaussian curve.
<code>alphacuts</code>	fixed by default to "FALSE". No alpha-cuts are printed in this case.
<code>margin</code>	an optional numerical couple of values representing the range of calculations of the Gaussian curve written as $[\text{mean} - 3 \cdot \sigma; \text{mean} + 3 \cdot \sigma]$ by default.
<code>step</code>	a numerical value fixing the step between two knots dividing the interval $[\text{mean} - 3 \cdot \sigma; \text{mean} + 3 \cdot \sigma]$.
<code>breakpoints</code>	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
<code>precision</code>	an integer specifying the number of decimals for which the calculations are made. These latter are set by default to be at the order of $1/10^4$.
<code>plot</code>	fixed by default to "FALSE". <code>plot="TRUE"</code> if a plot of the fuzzy number is required.

Value

If the parameter `alphacuts="TRUE"`, the function returns a matrix composed by 2 vectors representing the left and right alpha-cuts. For this output, `is.alphacuts = TRUE`. If the parameter `alphacuts="FALSE"`, the function returns a list composed by the Class, the mean, the sigma, the vectors of the left and right alpha-cuts.

Examples

```
GBFN <- GaussianBellFuzzyNumber(left.mean = -1, left.sigma = 1,
right.mean = 2, right.sigma = 1, alphacuts = TRUE, plot=TRUE)
is.alphacuts(GBFN)
```

GaussianFuzzyNumber	<i>Creates a Gaussian fuzzy number</i>
---------------------	--

Description

Creates a Gaussian fuzzy number

Usage

```
GaussianFuzzyNumber(
  mean,
  sigma,
  alphacuts = FALSE,
  margin = c(5, 5),
```

```

    step = 0.01,
    breakpoints = 100,
    precision = 4,
    plot = FALSE
  )

```

Arguments

mean	a numerical value of the parameter mu of the Gaussian curve.
sigma	a numerical value of the parameter sigma of the Gaussian curve.
alphacuts	fixed by default to "FALSE". No alpha-cuts are printed in this case.
margin	an optional numerical couple of values representing the range of calculations of the Gaussian curve written as [mean - 3*sigma; mean + 3*sigma] by default.
step	a numerical value fixing the step between two knots dividing the interval [mean - 3*sigma; mean + 3*sigma].
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
precision	an integer specifying the number of decimals for which the calculations are made. These latter are set by default to be at the order of $1/10^4$.
plot	fixed by default to "FALSE". plot="TRUE" if a plot of the fuzzy number is required.

Value

If the parameter alphacuts="TRUE", the function returns a matrix composed by 2 vectors representing the left and right alpha-cuts. For this output, is.alphacuts = TRUE. If the parameter alphacuts="FALSE", the function returns a list composed by the Class, the mean, the sigma, the vectors of the left and right alpha-cuts.

Examples

```

GFN <- GaussianFuzzyNumber(mean = 0, sigma = 1, alphacuts = TRUE, plot=TRUE)
is.alphacuts(GFN)

```

GFUZZ

Fuzzifies a variable modelled by any type of fuzzy numbers

Description

Fuzzifies a variable modelled by any type of fuzzy numbers

Usage

```
GFUZZ(data, mi, si, PA, spec = "Identical", breakpoints = 100)
```

Arguments

data	a data set.
mi	the index of the main-item containing the concerned variable.
si	the index of the sub-item of a given main-item mi.
PA	a vector of the linguistic terms of the considered variable.
spec	specification of the fuzzification matrix. The possible values are "Identical" and "Not Identical".
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. breakpoints is fixed to 100 by default.

Value

A numerical fuzzification array of 3 dimensions (m,n,2), with m lines, n columns and no NA.

Examples

```
data <- matrix(c(1,2,3,2,2,1,1,3,1,2),ncol=1)
MF111 <- TrapezoidalFuzzyNumber(0,1,1,2)
MF112 <- TrapezoidalFuzzyNumber(1,2,2,3)
MF113 <- TrapezoidalFuzzyNumber(2,3,3,3)
PA11 <- c(1,2,3)
data.fuzzified <- GFUZZ(data,mi=1,si=1,PA=PA11)
```

GLOB.EVAL

Calculates the global evaluation of a linguistic questionnaire

Description

Calculates the global evaluation of a linguistic questionnaire

Usage

```
GLOB.EVAL(
  Full_Database,
  MI,
  bmi,
  SI,
  b_jkt,
  p_ind = rep(1/nrow(Full_Database), nrow(Full_Database)),
  distance.type,
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

Full_Database	the data set to evaluate.
MI	a numerical value representing the total number of main-items dividing the linguistic questionnaire.
bmi	an array referring to the initial weights of the main-items.
SI	an array representing the total numbers of sub-items per main-item.
b_jkt	a matrix of MI rows and max(SI) columns expressing the initial weights of each sub-item of a given main-item.
p_ind	a vector of the relative sampling weights of the units, for which $length(p_{ind}) = nrow(data)$. If the weights are not relative, the following expression should be applied on the vector: $\frac{p_{ind}}{\sum_{i=1}^n p_{ind}}.$ If no sampling weights are used, the vector of weights is reduced to a vector of values 1, i.e. $rep(1, nrow(data))$.
distance.type	type of distance chosen from the family of distances, set by default to the signed distance. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
i	parameter of the density function of the Beta distribution, fixed by default to i = 1.
j	parameter of the density function of the Beta distribution, fixed by default to j = 1.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the Rho_p and Delta_pq.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A data set of individual evaluations, for which the number of observations is exactly the same as the initial data set.

Examples

```
data <- matrix(c(3,4,2,3,3,2,4,3,3,4,3,4,4,2,5,3,4,4,3,3,3,4,4,3,
3,3,4,3,3,3,3,4,4,3,5,3,4,3,3,3), ncol = 4)
```

```

data <- as.data.frame(data)
MI <- 2
SI1 <- 2
SI2 <- 2
SI <- c(SI1,SI2)
b_j <- c(1/2,1/2)
b_jk <- matrix(c(0.5,0.5,0.5,0.5),nrow=2)
PA11 <- c(1,2,3,4,5)
PA12 <- c(1,2,3,4,5)
PA21 <- c(1,2,3,4,5)
PA22 <- c(1,2,3,4,5)
# -----
MF111 <- TrapezoidalFuzzyNumber(0,2,2,7)
MF112 <- TrapezoidalFuzzyNumber(2,7,7,15)
MF113 <- TrapezoidalFuzzyNumber(7,15,15,23)
MF114 <- TrapezoidalFuzzyNumber(15,23,23,28)
MF115 <- TrapezoidalFuzzyNumber(23,28,28,30)
MF11 <- GFUZZ(data, 1, 1, PA11, spec="Identical", breakpoints = 100)
# -----
MF121 <- TrapezoidalFuzzyNumber(0,2,2,7)
MF122 <- TrapezoidalFuzzyNumber(2,7,7,15)
MF123 <- TrapezoidalFuzzyNumber(7,15,15,23)
MF124 <- TrapezoidalFuzzyNumber(15,23,23,28)
MF125 <- TrapezoidalFuzzyNumber(23,28,28,30)
MF12 <- GFUZZ(data, 1, 2, PA12, spec="Identical", breakpoints = 100)
# -----
MF211 <- TrapezoidalFuzzyNumber(0,2,2,7)
MF212 <- TrapezoidalFuzzyNumber(2,7,7,15)
MF213 <- TrapezoidalFuzzyNumber(7,15,15,23)
MF214 <- TrapezoidalFuzzyNumber(15,23,23,28)
MF215 <- TrapezoidalFuzzyNumber(23,28,28,30)
MF21 <- GFUZZ(data, 2, 1, PA21, spec="Identical", breakpoints = 100)
# -----
MF221 <- TrapezoidalFuzzyNumber(0,2,2,7)
MF222 <- TrapezoidalFuzzyNumber(2,7,7,15)
MF223 <- TrapezoidalFuzzyNumber(7,15,15,23)
MF224 <- TrapezoidalFuzzyNumber(15,23,23,28)
MF225 <- TrapezoidalFuzzyNumber(23,28,28,30)
MF22 <- GFUZZ(data, 2, 2, PA22, spec="Identical", breakpoints = 100)
# -----
range <- matrix(c(0,0,0,0,28,28,28,28), ncol=2)
ind.eval <- IND.EVAL(data,MI,b_j,SI,b_jk, range = range, distance.type ="DSGD.G")
GLOB <- GLOB.EVAL(data, MI, b_j, SI, b_jk, distance.type ="GSGD")

```

GLOB.EVAL.mean

*Calculates the weighted mean of the set of individual evaluations***Description**

Calculates the weighted mean of the set of individual evaluations

Usage

```
GLOB.EVAL.mean(ind.eval, weight = rep(1, length(ind.eval)))
```

Arguments

`ind.eval` the set of individual evaluations.

`weight` a vector of the relative sampling weights of the units, for which $length(weight) = length(ind.eval)$, set by default to $rep(1, length(ind.eval))$.

Value

An integer.

Examples

```
data <- matrix(c(3,4,2,3,3,2,4,3,3,4,3,4,4,2,5,3,4,4,3,3,3,4,4,3,
3,3,4,3,3,3,3,4,4,3,5,3,4,3,3,3), ncol = 4)
data <- as.data.frame(data)
MI <- 2
SI1 <- 2
SI2 <- 2
SI <- c(SI1, SI2)
b_j <- c(1/2, 1/2)
b_jk <- matrix(c(0.5, 0.5, 0.5, 0.5), nrow=2)
PA11 <- c(1, 2, 3, 4, 5)
PA12 <- c(1, 2, 3, 4, 5)
PA21 <- c(1, 2, 3, 4, 5)
PA22 <- c(1, 2, 3, 4, 5)
# -----
MF111 <- TrapezoidalFuzzyNumber(0, 2, 2, 7)
MF112 <- TrapezoidalFuzzyNumber(2, 7, 7, 15)
MF113 <- TrapezoidalFuzzyNumber(7, 15, 15, 23)
MF114 <- TrapezoidalFuzzyNumber(15, 23, 23, 28)
MF115 <- TrapezoidalFuzzyNumber(23, 28, 28, 30)
MF11 <- GFUZZ(data, 1, 1, PA11, spec="Identical", breakpoints = 100)
# -----
MF121 <- TrapezoidalFuzzyNumber(0, 2, 2, 7)
MF122 <- TrapezoidalFuzzyNumber(2, 7, 7, 15)
MF123 <- TrapezoidalFuzzyNumber(7, 15, 15, 23)
MF124 <- TrapezoidalFuzzyNumber(15, 23, 23, 28)
MF125 <- TrapezoidalFuzzyNumber(23, 28, 28, 30)
MF12 <- GFUZZ(data, 1, 2, PA12, spec="Identical", breakpoints = 100)
# -----
MF211 <- TrapezoidalFuzzyNumber(0, 2, 2, 7)
MF212 <- TrapezoidalFuzzyNumber(2, 7, 7, 15)
MF213 <- TrapezoidalFuzzyNumber(7, 15, 15, 23)
MF214 <- TrapezoidalFuzzyNumber(15, 23, 23, 28)
MF215 <- TrapezoidalFuzzyNumber(23, 28, 28, 30)
MF21 <- GFUZZ(data, 2, 1, PA21, spec="Identical", breakpoints = 100)
# -----
MF221 <- TrapezoidalFuzzyNumber(0, 2, 2, 7)
```

```
MF222 <- TrapezoidalFuzzyNumber(2,7,7,15)
MF223 <- TrapezoidalFuzzyNumber(7,15,15,23)
MF224 <- TrapezoidalFuzzyNumber(15,23,23,28)
MF225 <- TrapezoidalFuzzyNumber(23,28,28,30)
MF22 <- GFUZZ(data, 2, 2, PA22, spec="Identical", breakpoints = 100)
# -----
range <- matrix(c(0,0,0,0,28,28,28,28), ncol=2)
ind.eval <- IND.EVAL(data,MI,b_j,SI,b_jk, range = range, distance.type ="DSGD.G")
GLOB.mean <- GLOB.EVAL.mean(ind.eval)
```

GSGD

*Calculates the generalized signed distance between fuzzy numbers***Description**

Calculates the generalized signed distance between fuzzy numbers

Usage

```
GSGD(X, Y, i = 1, j = 1, thetas = 1, breakpoints = 100)
```

Arguments

X	a fuzzy number.
Y	a fuzzy number.
i	parameter of the density function of the Beta distribution, fixed by default to i = 1.
j	parameter of the density function of the Beta distribution, fixed by default to j = 1.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

IND.EVAL

*Calculates the individual evaluations of a linguistic questionnaire***Description**

Calculates the individual evaluations of a linguistic questionnaire

Usage

```
IND.EVAL(
  Full_Database,
  MI,
  bmi,
  SI,
  b_jkt,
  range,
  distance.type,
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100,
  spec = "Identical"
)
```

Arguments

Full_Database	the data set to evaluate.
MI	a numerical value representing the total number of main-items dividing the linguistic questionnaire.
bmi	an array referring to the initial weights of the main-items.
SI	an array representing the total numbers of sub-items per main-item.
b_jkt	a matrix of MI rows and max(SI) columns expressing the initial weights of each sub-item of a given main-item.
range	a vector of 2 elements giving the range of definition of the produced individual evaluations. The range is usually chosen in the interval between 0 and the maximum of the support set of all the membership functions modelling the data set.
distance.type	type of distance chosen from the family of distances, set by default to the signed distance. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
i	parameter of the density function of the Beta distribution, fixed by default to i = 1.

j	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to $1/3$ referring to the Lebesgue space. This measure is used in the calculations of the following distances: $d_Bertoluzza$, d_mid/spr and $d_phi-wabl/ldev/rdev$.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the Rho_p and Δ_{pq} .
q	a decimal value between 0 and 1, referring to the parameter of the metric Δ_{pq} .
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
spec	specification of the fuzzification matrix. The possible values are "Identical" and "Not Identical".

Value

A data set of individual evaluations, for which the number of observations is exactly the same as the initial data set.

Examples

```
data <- matrix(c(3,4,2,3,3,2,4,3,3,4,3,4,4,2,5,3,4,4,3,3,3,4,4,3,
3,3,4,3,3,3,3,4,4,3,5,3,4,3,3,3), ncol = 4)
data <- as.data.frame(data)
MI <- 2
SI1 <- 2
SI2 <- 2
SI <- c(SI1,SI2)
b_j <- c(1/2,1/2)
b_jk <- matrix(c(0.5,0.5,0.5,0.5),nrow=2)
PA11 <- c(1,2,3,4,5)
PA12 <- c(1,2,3,4,5)
PA21 <- c(1,2,3,4,5)
PA22 <- c(1,2,3,4,5)
# -----
MF111 <- TrapezoidalFuzzyNumber(0,2,2,7)
MF112 <- TrapezoidalFuzzyNumber(2,7,7,15)
MF113 <- TrapezoidalFuzzyNumber(7,15,15,23)
MF114 <- TrapezoidalFuzzyNumber(15,23,23,28)
MF115 <- TrapezoidalFuzzyNumber(23,28,28,30)
MF11 <- GFUZZ(data, 1, 1, PA11, spec="Identical", breakpoints = 100)
# -----
MF121 <- TrapezoidalFuzzyNumber(0,2,2,7)
MF122 <- TrapezoidalFuzzyNumber(2,7,7,15)
MF123 <- TrapezoidalFuzzyNumber(7,15,15,23)
MF124 <- TrapezoidalFuzzyNumber(15,23,23,28)
```

```

MF125 <- TrapezoidalFuzzyNumber(23,28,28,30)
MF12 <- GFUZZ(data, 1, 2, PA12, spec="Identical", breakpoints = 100)
# -----
MF211 <- TrapezoidalFuzzyNumber(0,2,2,7)
MF212 <- TrapezoidalFuzzyNumber(2,7,7,15)
MF213 <- TrapezoidalFuzzyNumber(7,15,15,23)
MF214 <- TrapezoidalFuzzyNumber(15,23,23,28)
MF215 <- TrapezoidalFuzzyNumber(23,28,28,30)
MF21 <- GFUZZ(data, 2, 1, PA21, spec="Identical", breakpoints = 100)
# -----
MF221 <- TrapezoidalFuzzyNumber(0,2,2,7)
MF222 <- TrapezoidalFuzzyNumber(2,7,7,15)
MF223 <- TrapezoidalFuzzyNumber(7,15,15,23)
MF224 <- TrapezoidalFuzzyNumber(15,23,23,28)
MF225 <- TrapezoidalFuzzyNumber(23,28,28,30)
MF22 <- GFUZZ(data, 2, 2, PA22, spec="Identical", breakpoints = 100)
# -----
range <- matrix(c(0,0,0,0,28,28,28,28), ncol=2)
ind.eval <- IND.EVAL(data,MI,b_j,SI,b_jk, range = range, distance.type ="DSGD.G")

```

int.0

Numerical integration by the trivial method - method 1

Description

Numerical integration by the trivial method - method 1

Usage

```
int.0(cut, a = 0, b = 1)
```

Arguments

cut	a vector.
a	fixed by default to 0.
b	fixed by default to 1.

Value

An integer.

int.ct	<i>Numerical integration by the composite trapezoidal method - method 3</i>
--------	---

Description

Numerical integration by the composite trapezoidal method - method 3

Usage

```
int.ct(cut, a = 0, b = 1)
```

Arguments

cut	a vector.
a	fixed by default to 0.
b	fixed by default to 1.

Value

An integer.

int.simpson	<i>Numerical integration by the Simpson method - method 4</i>
-------------	---

Description

Numerical integration by the Simpson method - method 4

Usage

```
int.simpson(alpha, cut, a = 0, b = 1)
```

Arguments

alpha	a vector of alpha values between 0 and 1.
cut	a vector.
a	fixed by default to 0.
b	fixed by default to 1.

Value

An integer.

int.t	Numerical integration - method 2
-------	----------------------------------

Description

Numerical integration - method 2

Usage

```
int.t(alpha, cut, a = 0, b = 1)
```

Arguments

alpha	a vector of alpha values between 0 and 1.
cut	a vector.
a	fixed by default to 0.
b	fixed by default to 1.

Value

An integer.

integrate.num	Numerical integration by a particular method
---------------	--

Description

Numerical integration by a particular method

Usage

```
integrate.num(alpha, cut, method, a = 0, b = 1)
```

Arguments

alpha	a vector of alpha values between 0 and 1.
cut	a vector.
method	the integration method could be one of the following four methods: "int.0", "int.t", "int.ct" and "int.simpson".
a	fixed by default to 0.
b	fixed by default to 1.

Value

An integer.

is.alphacuts	<i>Verifies if a matrix is set of left and right alpha-cuts</i>
--------------	---

Description

Verifies if a matrix is set of left and right alpha-cuts

Usage

```
is.alphacuts(data)
```

Arguments

data	a matrix of 2 equal length columns with no NA.
------	--

Value

A value TRUE if the concerned object can be a set of numerical left and right alpha-cuts, FALSE otherwise.

Examples

```
mat <- matrix(c(1,2,3,7,6,5), ncol = 2)
is.alphacuts(mat)
```

is.balanced	<i>Verifies if a design is balanced</i>
-------------	---

Description

Verifies if a design is balanced

Usage

```
is.balanced(ni)
```

Arguments

ni	a line array given by the contingency table related to the considered variable. Often written as a result of a call of the function table.
----	---

Value

Returns a logical decision TRUE or FALSE, to indicate if a given design is respectively balanced or not.

Examples

```
data <- matrix(c(1,2,3,2,2,1,1,3,1,2),ncol=1)
ni <- t(table(data))
is.balanced(ni)
```

is.fuzzification	<i>Verifies if a matrix is a fuzzification matrix</i>
------------------	---

Description

Verifies if a matrix is a fuzzification matrix

Usage

```
is.fuzzification(data)
```

Arguments

data an array of 3 dimensions c(m,n,2), with m lines, n columns. No NA are allowed.

Value

A value TRUE if the concerned object is a numerical fuzzification matrix, FALSE otherwise.

Examples

```
mat <- array(c(1,1,2,2,3,3,5,5,6,6,7,7),dim=c(2,3,2))
is.fuzzification(mat)
```

is.trfuzzification	<i>Verifies if a matrix is a fuzzification matrix of trapezoidal fuzzy numbers</i>
--------------------	--

Description

Verifies if a matrix is a fuzzification matrix of trapezoidal fuzzy numbers

Usage

```
is.trfuzzification(data)
```

Arguments

data a matrix of 4 columns (p,q,r,s), where $p \leq q \leq r \leq s$. No NA are allowed.

Value

A value TRUE if the concerned object is a trapezoidal or triangular fuzzification matrix, FALSE otherwise.

Examples

```
mat <- matrix(c(1,1,2,2,3,3,4,4),ncol=4)
is.trfuzzification(mat)
```

Kurtosis*Calculates the excess of kurtosis of a random fuzzy variable*

Description

Calculates the excess of kurtosis of a random fuzzy variable

Usage

```
Kurtosis(
  data.fuzzified,
  dist.type,
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

<code>data.fuzzified</code>	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
<code>dist.type</code>	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
<code>i</code>	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
<code>j</code>	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
<code>theta</code>	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: <code>d_Bertoluzza</code> , <code>d_mid/spr</code> and <code>d_phi-wabl/ldev/rdev</code> .

thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the Rho_p and Delta_pq. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq. By default, q is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

Examples

```
mat <- matrix(c(1,2,0.25,1.8,2,2.6,0.5,3,3,2.6,3.8,4,4,4.2,3.9,5), ncol =4)
Kurtosis(mat, dist.type = "GSGD")
```

Mid.Spr

Calculates a distance by the d_Mid.Spr between fuzzy numbers

Description

Calculates a distance by the d_Mid.Spr between fuzzy numbers

Usage

```
Mid.Spr(X, Y, i = 1, j = 1, theta = 1/3, breakpoints = 100)
```

Arguments

X	a fuzzy number.
Y	a fuzzy number.
i	parameter of the density function of the Beta distribution, fixed by default to i = 1.
j	parameter of the density function of the Beta distribution, fixed by default to j = 1.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

Moment	<i>Calculates a central sample moment of a random fuzzy variable</i>
--------	--

Description

Calculates a central sample moment of a random fuzzy variable

Usage

```
Moment(
  data.fuzzified,
  k,
  dist.type,
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

<code>data.fuzzified</code>	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
<code>k</code>	the order of the moment.
<code>dist.type</code>	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
<code>i</code>	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
<code>j</code>	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
<code>theta</code>	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: <code>d_Bertoluzza</code> , <code>d_mid/spr</code> and <code>d_phi-wabl/ldev/rdev</code> .
<code>thetas</code>	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the <code>d_theta star</code> and the <code>d_GSGD</code> distances.
<code>p</code>	a positive integer such that $1 \leq p < \text{infinity}$, referring to the parameter of the <code>Rho_p</code> and <code>Delta_pq</code> . By default, p is fixed to 2.
<code>q</code>	a decimal value between 0 and 1, referring to the parameter of the metric <code>Delta_pq</code> . By default, q is fixed to 0.5.

breakpoints a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

Examples

```
mat <- matrix(c(1,2,2,3,3,4,4,5), ncol =4)
Moment(mat, k=4, dist.type = "GSGD")
```

nbreakpoints	<i>Calculates the number of breakpoints of a numerical matrix of alpha-cuts</i>
--------------	---

Description

Calculates the number of breakpoints of a numerical matrix of alpha-cuts

Usage

```
nbreakpoints(data)
```

Arguments

data a matrix of numerical alpha-cuts or a 3-dimensional array. No NA are allowed.

Value

A numerical positive integer.

Examples

```
X <- TrapezoidalFuzzyNumber(1,2,3,4)
alpha.X <- alphacut(X, seq(0,1,0.01))
nbreakpoints(alpha.X)
```

n_jk..	<i>Calculates the number of answers by a specific sub-item</i>
--------	--

Description

Calculates the number of answers by a specific sub-item

Usage

```
n_jk..(x, varindex, PA, p_ind = rep(1, nrow(x)))
```

Arguments

x	the data set to evaluate.
varindex	index of a particular sub-item.
PA	set of possible linguistic terms.
p_ind	a vector of the relative sampling weights of the units, for which $length(p_ind) = nrow(data)$. If the weights are not relative, the following expression should be applied on the vector:

$$\frac{p_{ind}}{\sum_{i=1}^n p_{ind}}.$$

If no sampling weights are used, the vector of weights is reduced to a vector of values 1, i.e. $rep(1, nrow(data))$.

Value

A positive integer.

n_jkq.	<i>Calculates the number of answers by a specific linguistic of a sub-item</i>
--------	--

Description

Calculates the number of answers by a specific linguistic of a sub-item

Usage

```
n_jkq.(x, varindex, q, p_ind = rep(1, nrow(x)))
```

Arguments

x	the data set to evaluate.
varindex	index of a particular sub-item.
q	index of a particular linguistic term.
p_ind	a vector of the relative sampling weights of the units, for which $length(p_ind) = nrow(data)$. If the weights are not relative, the following expression should be applied on the vector:

$$\frac{p_{ind}}{\sum_{i=1}^n p_{ind}}.$$

If no sampling weights are used, the vector of weights is reduced to a vector of values 1, i.e. $rep(1, nrow(data))$.

Value

A positive integer.

optimal.distance	<i>Calculates the optimal distance between two fuzzy numbers according to the chosen type</i>
------------------	---

Description

Calculates the optimal distance between two fuzzy numbers according to the chosen type

Usage

```
optimal.distance(
  X,
  Y,
  type = "DSGD.G",
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

X	a fuzzy number.
Y	a fuzzy number.
type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".

i	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
j	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to $1/3$ referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \text{infinity}$, referring to the parameter of the Rho_p and Delta_pq.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

Examples

```
X <- TrapezoidalFuzzyNumber(1,2,3,4)
Y <- TrapezoidalFuzzyNumber(4,5,6,7)
optimal.distance(X, Y, type = "GSGD")
optimal.distance(X, Y, type = "Bertoluzza")
```

p.value.fisher	<i>Calculates the p-value of fuzzy observations taken from a Fisher distribution</i>
----------------	--

Description

Calculates the p-value of fuzzy observations taken from a Fisher distribution

Usage

```
p.value.fisher(
  type,
  H0,
  H1,
  t,
  n,
  r,
  s.d,
```

```

    sig,
    dist.type,
    i = 1,
    j = 1,
    theta = 1/3,
    thetas = 1,
    p = 2,
    q = 0.5,
    breakpoints = 100
)

```

Arguments

type	a category between "0", "1" and "2". The category "0" refers to a bilateral test, the category "1" for a lower unilateral one, and "2" for an upper unilateral test.
H0	a trapezoidal or a triangular fuzzy number representing the fuzzy null hypothesis.
H1	a trapezoidal or a triangular fuzzy number representing the fuzzy alternative hypothesis.
t	a given numerical or fuzzy type parameter of the distribution.
n	first degree of freedom.
r	second degree of freedom.
s.d	a numerical value for the standard deviation of the distribution.
sig	a numerical value representing the significance level of the test.
dist.type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
i	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
j	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the Rho_p and Delta_pq. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq. By default, p is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

Returns the defuzzified p-value and the decision made.

p.value.log	<i>Calculates the p-value of fuzzy observations taken from a Logistic distribution</i>
-------------	--

Description

Calculates the p-value of fuzzy observations taken from a Logistic distribution

Usage

```
p.value.log(
  type,
  H0,
  H1,
  t,
  n,
  s.d,
  sig,
  dist.type,
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

type	a category between "0", "1" and "2". The category "0" refers to a bilateral test, the category "1" for a lower unilateral one, and "2" for an upper unilateral test.
H0	a trapezoidal or a triangular fuzzy number representing the fuzzy null hypothesis.
H1	a trapezoidal or a triangular fuzzy number representing the fuzzy alternative hypothesis.
t	a given numerical or fuzzy type parameter of the distribution.
n	the total number of observations of the data set.
s.d	a numerical value for the standard deviation of the distribution.
sig	a numerical value representing the significance level of the test.

<code>dist.type</code>	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
<code>i</code>	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
<code>j</code>	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
<code>theta</code>	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to $1/3$ referring to the Lebesgue space. This measure is used in the calculations of the following distances: <code>d_Bertoluzza</code> , <code>d_mid/spr</code> and <code>d_phi-wabl/ldev/rdev</code> .
<code>thetas</code>	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the <code>d_theta star</code> and the <code>d_GSGD</code> distances.
<code>p</code>	a positive integer such that $1 \leq p < \text{infinity}$, referring to the parameter of the <code>Rho_p</code> and <code>Delta_pq</code> . By default, <code>p</code> is fixed to 2.
<code>q</code>	a decimal value between 0 and 1, referring to the parameter of the metric <code>Delta_pq</code> . By default, <code>p</code> is fixed to 0.5.
<code>breakpoints</code>	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

Returns the defuzzified p-value and the decision made.

<code>p.value.mean.log</code>	<i>Calculates the p-value of fuzzy observations taken from a logistic distribution for the mean</i>
-------------------------------	---

Description

Calculates the p-value of fuzzy observations taken from a logistic distribution for the mean

Usage

```
p.value.mean.log(
  data.fuzzified,
  type,
  H0,
  H1,
  s.d,
  sig,
  dist.type,
  i = 1,
  j = 1,
```

```

    theta = 1/3,
    thetas = 1,
    p = 2,
    q = 0.5,
    breakpoints = 100
)

```

Arguments

data.fuzzified	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
type	a category between "0", "1" and "2". The category "0" refers to a bilateral test, the category "1" for a lower unilateral one, and "2" for an upper unilateral test.
H0	a trapezoidal or a triangular fuzzy number representing the fuzzy null hypothesis.
H1	a trapezoidal or a triangular fuzzy number representing the fuzzy alternative hypothesis.
s.d	a numerical value for the standard deviation of the distribution.
sig	a numerical value representing the significance level of the test.
dist.type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
i	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
j	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the Rho_p and Delta_pq. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq. By default, q is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

Returns the defuzzified p-value and the decision made.

p.value.mean.normal	<i>Calculates the p-value of fuzzy observations taken from a normal distribution for the mean</i>
---------------------	---

Description

Calculates the p-value of fuzzy observations taken from a normal distribution for the mean

Usage

```
p.value.mean.normal(
  data.fuzzified,
  type,
  H0,
  H1,
  s.d,
  sig,
  dist.type,
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

data.fuzzified	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
type	a category between "0", "1" and "2". The category "0" refers to a bilateral test, the category "1" for a lower unilateral one, and "2" for an upper unilateral test.
H0	a trapezoidal or a triangular fuzzy number representing the fuzzy null hypothesis.
H1	a trapezoidal or a triangular fuzzy number representing the fuzzy alternative hypothesis.
s.d	a numerical value for the standard deviation of the distribution.
sig	a numerical value representing the significance level of the test.
dist.type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
i	parameter of the density function of the Beta distribution, fixed by default to i = 1.

j	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to $1/3$ referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the Rho_p and Delta_pq. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq. By default, q is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

Returns the defuzzified p-value and the decision made.

p.value.mean.poisson	<i>Calculates the p-value of fuzzy observations taken from a Poisson distribution for the mean</i>
----------------------	--

Description

Calculates the p-value of fuzzy observations taken from a Poisson distribution for the mean

Usage

```
p.value.mean.poisson(
  data.fuzzified,
  type,
  H0,
  H1,
  sig,
  dist.type,
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

<code>data.fuzzified</code>	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
<code>type</code>	a category between "0", "1" and "2". The category "0" refers to a bilateral test, the category "1" for a lower unilateral one, and "2" for an upper unilateral test.
<code>H0</code>	a trapezoidal or a triangular fuzzy number representing the fuzzy null hypothesis.
<code>H1</code>	a trapezoidal or a triangular fuzzy number representing the fuzzy alternative hypothesis.
<code>sig</code>	a numerical value representing the significance level of the test.
<code>dist.type</code>	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
<code>i</code>	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
<code>j</code>	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
<code>theta</code>	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: <code>d_Bertoluzza</code> , <code>d_mid/spr</code> and <code>d_phi-wabl/ldev/rdev</code> .
<code>thetas</code>	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the <code>d_theta star</code> and the <code>d_GSGD</code> distances.
<code>p</code>	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the <code>Rho_p</code> and <code>Delta_pq</code> . By default, p is fixed to 2.
<code>q</code>	a decimal value between 0 and 1, referring to the parameter of the metric <code>Delta_pq</code> . By default, p is fixed to 0.5.
<code>breakpoints</code>	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

Returns the defuzzified p-value and the decision made.

<code>p.value.mean.Student</code>	<i>Calculates the p-value of fuzzy observations taken from a Student distribution for the mean</i>
-----------------------------------	--

Description

Calculates the p-value of fuzzy observations taken from a Student distribution for the mean

Usage

```
p.value.mean.Student(
  data.fuzzified,
  type,
  H0,
  H1,
  sig,
  dist.type,
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

data.fuzzified	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
type	a category between "0", "1" and "2". The category "0" refers to a bilateral test, the category "1" for a lower unilateral one, and "2" for an upper unilateral test.
H0	a trapezoidal or a triangular fuzzy number representing the fuzzy null hypothesis.
H1	a trapezoidal or a triangular fuzzy number representing the fuzzy alternative hypothesis.
sig	a numerical value representing the significance level of the test.
dist.type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
i	parameter of the density function of the Beta distribution, fixed by default to i = 1.
j	parameter of the density function of the Beta distribution, fixed by default to j = 1.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the Rho_p and Delta_pq. By default, p is fixed to 2.

q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq. By default, p is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

Returns the defuzzified p-value and the decision made.

p.value.normal	<i>Calculates the p-value of fuzzy observations taken from a normal distribution</i>
----------------	--

Description

Calculates the p-value of fuzzy observations taken from a normal distribution

Usage

```
p.value.normal(  
  type,  
  H0,  
  H1,  
  t,  
  n,  
  s.d,  
  sig,  
  dist.type,  
  i = 1,  
  j = 1,  
  theta = 1/3,  
  thetas = 1,  
  p = 2,  
  q = 0.5,  
  breakpoints = 100  
)
```

Arguments

type	a category between "0", "1" and "2". The category "0" refers to a bilateral test, the category "1" for a lower unilateral one, and "2" for an upper unilateral test.
H0	a trapezoidal or a triangular fuzzy number representing the fuzzy null hypothesis.
H1	a trapezoidal or a triangular fuzzy number representing the fuzzy alternative hypothesis.
t	a given numerical or fuzzy type parameter of the distribution.

n	the total number of observations of the data set.
s.d	a numerical value for the standard deviation of the distribution.
sig	a numerical value representing the significance level of the test.
dist.type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
i	parameter of the density function of the Beta distribution, fixed by default to i = 1.
j	parameter of the density function of the Beta distribution, fixed by default to j = 1.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the Rho_p and Delta_pq. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq. By default, p is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

Returns the defuzzified p-value and the decision made.

p.value.poisson	<i>Calculates the p-value of fuzzy observations taken from a Poisson distribution</i>
-----------------	---

Description

Calculates the p-value of fuzzy observations taken from a Poisson distribution

Usage

```
p.value.poisson(
  type,
  H0,
  H1,
  t,
  n,
```

```

sig,
dist.type,
i = 1,
j = 1,
theta = 1/3,
thetas = 1,
p = 2,
q = 0.5,
breakpoints = 100,
s.d = 1
)

```

Arguments

type	a category between "0", "1" and "2". The category "0" refers to a bilateral test, the category "1" for a lower unilateral one, and "2" for an upper unilateral test.
H0	a trapezoidal or a triangular fuzzy number representing the fuzzy null hypothesis.
H1	a trapezoidal or a triangular fuzzy number representing the fuzzy alternative hypothesis.
t	a given numerical or fuzzy type parameter of the distribution.
n	the total number of observations of the data set.
sig	a numerical value representing the significance level of the test.
dist.type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
i	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
j	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: $d_{Bertoluzza}$, $d_{mid/spr}$ and $d_{phi-wabl/ldev/rdev}$.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_{theta} star and the d_{GSGD} distances.
p	a positive integer such that $1 \leq p < \infty$, referring to the parameter of the Rho_p and $Delta_{pq}$. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric $Delta_{pq}$. By default, p is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
s.d	a numerical value for the standard deviation of the distribution.

Value

Returns the defuzzified p-value and the decision made.

p.value.Student	<i>Calculates the p-value of fuzzy observations taken from a Student distribution</i>
-----------------	---

Description

Calculates the p-value of fuzzy observations taken from a Student distribution

Usage

```
p.value.Student(
  type,
  H0,
  H1,
  t,
  n,
  sig,
  dist.type,
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100,
  s.d = 1
)
```

Arguments

type	a category between "0", "1" and "2". The category "0" refers to a bilateral test, the category "1" for a lower unilateral one, and "2" for an upper unilateral test.
H0	a trapezoidal or a triangular fuzzy number representing the fuzzy null hypothesis.
H1	a trapezoidal or a triangular fuzzy number representing the fuzzy alternative hypothesis.
t	a given numerical or fuzzy type parameter of the distribution.
n	the total number of observations of the data set.
sig	a numerical value representing the significance level of the test.
dist.type	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".

i	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
j	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
thetas	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the d_theta star and the d_GSGD distances.
p	a positive integer such that $1 \leq p < \text{infinity}$, referring to the parameter of the Rho_p and Delta_pq. By default, p is fixed to 2.
q	a decimal value between 0 and 1, referring to the parameter of the metric Delta_pq. By default, p is fixed to 0.5.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
s.d	a numerical value for the standard deviation of the distribution.

Value

Returns the defuzzified p-value and the decision made.

prm_polygon	<i>Polygon Ranking Method for two convex polygonal fuzzy numbers</i>
-------------	--

Description

Computes the Polygon Ranking Method (PRM) distance and score between two fuzzy numbers whose membership functions are convex polygons (i.e. any piecewise-linear, unimodal membership function: triangular, trapezoidal, or general polygonal). This is the workhorse function of the package; prm_triangle and prm_trapezoid are convenience wrappers around it for the two most common special cases.

Usage

prm_polygon(v1, v2, eps = 1e-06)

Arguments

v1, v2 Two-column numeric matrices (x, mu) giving the vertices of each fuzzy number's membership function, ordered by non-decreasing x. mu should rise from 0 to 1 and fall back to 0 (or more generally describe a convex, unimodal shape); the first and last row will typically have mu = 0. Validated on entry: both matrices must have exactly 2 columns, x non-decreasing, mu in [0, 1], and each must

reach $\mu = 1$ somewhere (prm_polygon assumes *normal* convex fuzzy numbers, as does the rest of the package); violations raise an informative error rather than propagating into a cryptic failure inside cumfun_polygon.

eps Numeric, base relative half-width used to regularize degenerate input (crisp numbers, duplicated abscissae); see normalize_polygon. The *effective* half-width used internally is eps scaled up by the magnitude of the input values ($\text{eps} * \max(1, \max(\text{abs}(v1[, 1]), \text{abs}(v2[, 1])))$), so that e.g. comparing two crisp numbers around 1000 does not force interpolation slopes of order $1/\text{eps}$ that would swamp the fixed tolerances used elsewhere in the computation (see "Numerical note" below). Default $1e-6$ (i.e. a half-width of about one part per million of the input's magnitude).

Details

For each fuzzy number, let $\mu(x)$ be its membership function, $M(x) = \int_{-\infty}^x \mu(t) dt$ its cumulative function, and A the total area under μ ($A = M(\infty)$). Let x^* be the representative ("core") point of the fuzzy number, computed as the mean of the abscissae where $\mu = 1$ (a single point for a triangular number, the midpoint of the plateau for a trapezoidal one).

Writing $G(x) = M_1(x) - M_2(x)$, the PRM distance is split into:

D_dir the *directional* contribution, $G(x_1^*) + G(x_2^*) - (A_1 - A_2)$, which is positive when the first fuzzy number tends to be smaller than the second, negative when it tends to be larger, and (near) zero when they are indifferent.

D_core the *core* (ambiguity) contribution, the total variation of G over $[\min(x_1^*, x_2^*), \max(x_1^*, x_2^*)]$, which grows with how much the two membership functions overlap/cross each other.

with $D_{PRM} = D_{dir} + D_{core}$. Dividing each distance by $A_1 + A_2$ gives the corresponding scores S_{dir} , S_{core} , S_{PRM} , which are scale-free and comparable across different pairs of fuzzy numbers, with $-1 \leq S_{dir} \leq 1$ and $-1 \leq S_{PRM} \leq 1$; both bounds are attained exactly when $v1$ and $v2$ have disjoint supports (Donze, Theorems 2 and 4).

The confidence index $C = |S_{dir}| / (|S_{dir}| + S_{core})$ (computed by summary_prm / summary_prm_scores, not returned here) measures how much of the total distance is directional rather than ambiguous: C close to 1 signals a strong, unambiguous ranking, C close to 0 a highly ambiguous one.

Value

A named list with components:

D_dir, D_core, D_PRM Directional, core and total PRM distances (see Details). NA when both $v1$ and $v2$ are crisp (see "Numerical note" below): the unnormalized distances are a genuine 0/0 form in that limit.

S_dir, S_core, S_PRM The corresponding scores, normalized by $\text{Area1} + \text{Area2}$.

Direction $\text{sign}(D_{dir})$: 1 if $v1$ tends to rank below $v2$, -1 if above, 0 if tied.

Decision A character string summarizing the ranking: " $x1 < x2$ ", " $x1 > x2$ ", or " $x1 \sim x2$ ".

Area1, Area2 Total area under each membership function.

Core1, Core2 The representative ("core") point of each fuzzy number.

Crossings Sorted numeric vector of the abscissae where the two membership functions intersect (possibly empty).

Partition Sorted numeric vector of the breakpoints used to compute D_{core} (see `sign_partition_polygon`).

Numerical note

comparing crisp (or near-crisp) numbers: When **both** v_1 and v_2 are crisp (each a single, repeated abscissa), `prm_polygon` bypasses the generic polygon machinery entirely and returns the exact closed-form limit derived in Donze (draft, Section 3): $S_{\text{core}} = 0$, $S_{\text{dir}} = \text{sign}(x_2 - x_1)$, $S_{\text{PRM}} = \text{abs}(S_{\text{dir}})$, so that the PRM ranking coincides exactly with the usual ordering of $\mathbb{R}$. In that case D_{dir} , D_{core} , D_{PRM} are set to NA: the unnormalized distances are a genuine 0/0 form in the true crisp limit (both areas vanish), so only the normalized scores are mathematically defined; use those.

When only **one** of v_1 , v_2 is crisp (the other remains genuinely fuzzy), the generic path below still applies, and the crisp side is regularized internally as a symmetric triangle of half-width `eps'` (the scaled `\code{eps}` described above) around its value. This is mathematically exact in the limit `\code{eps}' -> 0`, but at fixed finite precision an `eps'` that is tiny relative to the crisp value forces an interpolation slope of order `\code{1/eps}'` inside `cumfun_polygon`, and computing areas from such slopes subtracts two large intermediate quantities to recover a tiny true answer (catastrophic cancellation). `eps = 1e-6` is a compromise that keeps the regularization tight while keeping this effect negligible for typical inputs; if you see an out-of-range score (e.g. a negative S_{core}) when comparing a crisp number against a fuzzy one of very large or very small magnitude, try increasing `eps` further.

Note

D_{dir} (hence S_{dir} , Direction and Decision) is antisymmetric in its two arguments ($D_{\text{dir}}(\tilde{x}_1, \tilde{x}_2) = -D_{\text{dir}}(\tilde{x}_2, \tilde{x}_1)$) and D_{core} is symmetric, but D_{PRM} itself is **not** antisymmetric: in general $D_{\text{PRM}}(\tilde{x}_1, \tilde{x}_2) \neq -D_{\text{PRM}}(\tilde{x}_2, \tilde{x}_1)$, only $D_{\text{PRM}}(\tilde{x}_1, \tilde{x}_2) - D_{\text{PRM}}(\tilde{x}_2, \tilde{x}_1) = 2D_{\text{dir}}(\tilde{x}_1, \tilde{x}_2)$ (Donze, Theorem 3). Swapping v_1 and v_2 therefore flips the sign of $D_{\text{dir}}/S_{\text{dir}}$ /Direction and the direction of Decision, but $D_{\text{core}}/S_{\text{core}}$ are unchanged and $D_{\text{PRM}}/S_{\text{PRM}}$ do not simply change sign.

References

Donze, L. (2026). *Ranking fuzzy numbers with the Polygon Ranking Method (PRM)*. Working paper, University of Fribourg.

Berkachy, R., Donze, L. (2024). Generalisation of the signed distance. *Mathematics*, 12(24), 4042. [doi:10.3390/math12244042](https://doi.org/10.3390/math12244042)

See Also

`prm_triangle`, `prm_trapezoid` for convenience wrappers; `summary_prm` and `summary_prm_scores` to format the result.

Examples

```
# Two triangular fuzzy numbers, built "by hand" as polygons
v1 <- matrix(c(3, 0, 5, 1, 5, 1, 6, 0), ncol = 2, byrow = TRUE)
v2 <- matrix(c(-2, 0, -1, 1, -1, 1, 1, 0), ncol = 2, byrow = TRUE)
res <- prm_polygon(v1, v2)
```

```

res$Decision
summary_prm(res)

# Two crisp numbers: exact closed form, coincides with the usual
# ordering of the reals
summary_prm(prm_triangle(c(5, 5, 5), c(8, 8, 8)))

```

prn_trapezoid

PRM ranking of two trapezoidal fuzzy numbers

Description

Convenience wrapper around `prn_polygon` for trapezoidal fuzzy numbers, specified by their four defining points (a, b, c, d) with $a \leq b \leq c \leq d$: membership rises linearly from 0 at a to 1 at b , stays at 1 between b and c , then falls linearly back to 0 at d . (Setting $b = c$ recovers a triangular fuzzy number.)

Usage

```
prn_trapezoid(v1, v2, eps = 1e-06)
```

Arguments

<code>v1, v2</code>	Numeric vectors of length 4, $c(a, b, c, d)$, giving the four defining points of each trapezoidal fuzzy number. Named <code>v1/v2</code> for consistency with <code>prn_polygon</code> and <code>prn_triangle</code> : argument 1 always describes $\tilde{x}_1$, argument 2 always describes $\tilde{x}_2$.
<code>eps</code>	Passed to <code>prn_polygon</code> ; only matters when <code>v1</code> or <code>v2</code> is crisp ($a == b == c == d$).

Value

See `prn_polygon`.

See Also

`prn_polygon`, `prn_triangle`

Examples

```

res <- prn_trapezoid(c(3, 5, 5, 6), c(-2, -1, -1, 1))
summary_prm(res)

```

prm_triangle	<i>PRM ranking of two triangular fuzzy numbers</i>
--------------	--

Description

Convenience wrapper around prm_polygon for triangular fuzzy numbers, specified by their three defining points (a, b, c) with $a \leq b \leq c$: membership rises linearly from 0 at a to 1 at b , then falls linearly back to 0 at c .

Usage

```
prm_triangle(v1, v2, eps = 1e-06)
```

Arguments

v1, v2	Numeric vectors of length 3, $c(a, b, c)$, giving the left, peak and right points of each triangular fuzzy number. Named v1/v2 for consistency with prm_polygon and prm_trapezoid: argument 1 always describes $\tilde{x}_1$, argument 2 always describes $\tilde{x}_2$.
eps	Passed to prm_polygon; only matters when v1 or v2 is crisp ($a == b == c$).

Value

See prm_polygon.

See Also

prm_polygon, prm_trapezoid

Examples

```
res <- prm_triangle(c(1, 3, 6), c(4, 7, 9))
summary_prm(res)
```

R	<i>Calculates the indicator of information's rate of the data base</i>
---	--

Description

Calculates the indicator of information's rate of the data base

Usage

```
R(x, p_ind, b_jk, SI)
```

Arguments

x the data set to evaluate.

p_ind a vector of the relative sampling weights of the units, for which $length(p_ind) = nrow(data)$. If the weights are not relative, the following expression should be applied on the vector:

$$\frac{p_{ind}}{\sum_{i=1}^n p_{ind}}.$$

If no sampling weights are used, the vector of weights is reduced to a vector of values 1, i.e. $rep(1, nrow(data))$.

b_jk a matrix of length(b_j) rows and max(SI) columns expressing the initial weights of each sub-item of a given main-item.

SI an array representing the total numbers of sub-items per main-item.

Value

A numerical value giving the indicator of information's rate of the complete linguistic questionnaire. Note that the obtained value is interpreted as the more it tends to the value 1, the less the complete questionnaire contains missing values.

Examples

```
data <- matrix(c(3,4,2,3,3,2,4,3,3,4,3,4,4,2,5,3,4,4,3,3,3,4,4,3,
3,3,4,3,3,3,3,4,4,3,5,3,4,3,3,3), ncol = 4)
data <- as.data.frame(data)
p_ind <- c(0.1,0.05,0.05,0.2,0.1,0.05,0.1,0.1,0.2,0.05)
SI1 <- 2
SI2 <- 2
SI <- c(SI1,SI2)
b_jk <- matrix(c(0.5,0.5,0.5,0.5),nrow=2)
R(data, p_ind, b_jk, SI)
```

Rho1

*Calculates a distance by the Rho1 between fuzzy numbers***Description**

Calculates a distance by the Rho1 between fuzzy numbers

Usage

```
Rho1(X, Y, breakpoints = 100)
```

Arguments

X a fuzzy number.

Y a fuzzy number.

breakpoints a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

Rho2

Calculates a distance by the Rho2 between fuzzy numbers

Description

Calculates a distance by the Rho2 between fuzzy numbers

Usage

Rho2(X, Y, breakpoints = 100)

Arguments

X	a fuzzy number.
Y	a fuzzy number.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

Rhop

Calculates a distance by the d_Rhop between fuzzy numbers

Description

Calculates a distance by the d_Rhop between fuzzy numbers

Usage

Rhop(X, Y, p, breakpoints = 100)

Arguments

X	a fuzzy number.
Y	a fuzzy number.
p	a positive integer such that $1 \leq p < \text{infinity}$, referring to the parameter of the Rho_p and Delta_pq.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

Ri	<i>Calculates the indicator of information's rate of the data base for a given unit</i>
----	---

Description

Calculates the indicator of information's rate of the data base for a given unit

Usage

Ri(x, i, b_jk, SI)

Arguments

- x the data set to evaluate.
- i an observation index.
- b_jk a matrix of length(b_j) rows and max(SI) columns expressing the initial weights of each sub-item of a given main-item.
- SI an array representing the total numbers of sub-items per main-item.

Value

A numerical value giving the indicator of information's rate of the complete linguistic questionnaire for a particular observation. Note that the obtained value is interpreted as the more it tends to the value 1, the less the observation i contains missing values.

Examples

```
data <- matrix(c(3,4,2,3,3,2,4,3,3,4,3,4,4,2,5,3,4,4,3,3,3,4,4,3,
3,3,4,3,3,3,3,4,4,3,5,3,4,3,3,3), ncol = 4)
data <- as.data.frame(data)
SI1 <- 2
SI2 <- 2
SI <- c(SI1,SI2)
b_jk <- matrix(c(0.5,0.5,0.5,0.5),nrow=2)
Ri(data, 7, b_jk, SI)
```

Sample.variance	<i>Calculates the sample variance by a convenient metric</i>
-----------------	--

Description

Calculates the sample variance by a convenient metric

Usage

```
Sample.variance(
  data.fuzzified,
  dist.type,
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

<code>data.fuzzified</code>	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
<code>dist.type</code>	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
<code>i</code>	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
<code>j</code>	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
<code>theta</code>	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: <code>d_Bertoluzza</code> , <code>d_mid/spr</code> and <code>d_phi-wabl/ldev/rdev</code> .
<code>thetas</code>	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the <code>d_theta star</code> and the <code>d_GSGD</code> distances.
<code>p</code>	a positive integer such that $1 \leq p < \text{infinity}$, referring to the parameter of the <code>Rho_p</code> and <code>Delta_pq</code> . By default, p is fixed to 2.
<code>q</code>	a decimal value between 0 and 1, referring to the parameter of the metric <code>Delta_pq</code> . By default, q is fixed to 0.5.
<code>breakpoints</code>	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

SEQ.ORDERING

Calculates the sequential sums of squares by a convenient metric

Description

Calculates the sequential sums of squares by a convenient metric

Usage

SEQ.ORDERING(scope, data, f.response)

Arguments

scope	a description of the complete fitting model.
data	the data frame containing all the variables of the model.
f.response	the vector of distances of the fuzzy response variable to the fuzzy origin.

Value

Returns a list of the new sets of sums of squares, as well as the coefficients, the residuals and the fitted.values.

SEQ.ORDERING.APPROXIMATION

Calculates the sequential sums of squares by an approximation

Description

Calculates the sequential sums of squares by an approximation

Usage

SEQ.ORDERING.APPROXIMATION(scope, data, f.response)

Arguments

scope	a description of the complete fitting model.
data	the data frame containing all the variables of the model.
f.response	the vector of distances of the fuzzy response variable to the fuzzy origin.

Value

Returns a list of the new sets of sums of squares, as well as the coefficients, the residuals and the fitted.values.

SEQ.ORDERING.EXACT	<i>Calculates the sequential sums of squares by an exact calculation</i>
--------------------	--

Description

Calculates the sequential sums of squares by an exact calculation

Usage

```
SEQ.ORDERING.EXACT(scope, data, f.response)
```

Arguments

scope	a description of the complete fitting model.
data	the data frame containing all the variables of the model.
f.response	the vector of distances of the fuzzy response variable to the fuzzy origin.

Value

Returns a list of the new sets of sums of squares, as well as the coefficients, the residuals and the fitted.values.

SGD	<i>Calculates a distance by the SGD between fuzzy numbers</i>
-----	---

Description

Calculates a distance by the SGD between fuzzy numbers

Usage

```
SGD(X, i = 1, j = 1, breakpoints = 100)
```

Arguments

X	a fuzzy number.
i	parameter of the density function of the Beta distribution, fixed by default to i = 1.
j	parameter of the density function of the Beta distribution, fixed by default to j = 1.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

Skewness

Calculates the skewness of a random fuzzy variable

Description

Calculates the skewness of a random fuzzy variable

Usage

```
Skewness(
  data.fuzzified,
  dist.type,
  i = 1,
  j = 1,
  theta = 1/3,
  thetas = 1,
  p = 2,
  q = 0.5,
  breakpoints = 100
)
```

Arguments

<code>data.fuzzified</code>	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
<code>dist.type</code>	type of distance chosen from the family of distances. The different choices are given by: "Rho1", "Rho2", "Bertoluzza", "Rhop", "Delta.pq", "Mid/Spr", "wabl", "DSGD", "DSGD.G", "GSGD".
<code>i</code>	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
<code>j</code>	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
<code>theta</code>	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to 1/3 referring to the Lebesgue space. This measure is used in the calculations of the following distances: <code>d_Bertoluzza</code> , <code>d_mid/spr</code> and <code>d_phi-wabl/ldev/rdev</code> .
<code>thetas</code>	a decimal value between 0 and 1, representing the weight given to the shape of the fuzzy number. By default, thetas is fixed to 1. This parameter is used in the calculations of the <code>d_theta star</code> and the <code>d_GSGD</code> distances.
<code>p</code>	a positive integer such that $1 \leq p < \text{infinity}$, referring to the parameter of the <code>Rho_p</code> and <code>Delta_pq</code> . By default, p is fixed to 2.
<code>q</code>	a decimal value between 0 and 1, referring to the parameter of the metric <code>Delta_pq</code> . By default, q is fixed to 0.5.
<code>breakpoints</code>	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

Examples

```
mat <- matrix(c(1,2,0.25,1.8,2,2.6,0.5,3,3,2.6,3.8,4,4,4.2,3.9,5), ncol =4)
Skewness(mat, dist.type = "GSGD")
```

square	<i>Square a number</i>
--------	------------------------

Description

Takes any numerical value and squares it.

Usage

```
square(x)
```

Arguments

x A numeric value to be squared

Value

The square of the input

summary_prm	<i>Full summary table of a PRM result</i>
-------------	---

Description

Formats the list returned by prm_polygon (or its wrappers prm_triangle / prm_trapezoid) into a single-row data.frame, rounding numeric quantities and collapsing the Crossings and Partition vectors into readable strings.

Usage

```
summary_prm(res, digits = 6)
```

Arguments

res A list as returned by prm_polygon.
digits Integer, number of digits used to round numeric columns (default 6).

Value

A one-row data.frame with columns Core1, Core2, Area1, Area2, D_dir, D_core, D_PRM, S_dir, S_core, S_PRM, C (share of the total distance that is directional, i.e. $|S_{dir}|/(|S_{dir}| + S_{core})$; NA when both are zero), Direction, Decision, Ncross (number of crossing points), Crossings (comma-separated string), Nintervals (number of sign-partition intervals) and Partition (comma-separated string).

See Also

summary_prm_scores for a compact, scores-only version.

Examples

```
summary_prm(prm_triangle(c(1, 3, 6), c(4, 7, 9)))
```

summary_prm_scores	<i>Score-only summary of a PRM result</i>
--------------------	---

Description

A compact alternative to summary_prm that only reports the normalized PRM scores, useful when the areas, cores, crossings and partition details are not needed (e.g. when batch-ranking many pairs of fuzzy numbers).

Usage

```
summary_prm_scores(res, digits = 6)
```

Arguments

- res A list as returned by prm_polygon.
- digits Integer, number of digits used to round numeric columns (default 6).

Value

A one-row data.frame with columns S_dir, S_core, S_PRM and C (see summary_prm for their definition).

See Also

summary_prm

Examples

```
summary_prm_scores(prm_triangle(c(1, 3, 6), c(4, 7, 9)))
```

<code>tr.gfuzz</code>	<i>Fuzzifies a variable modelled by trapezoidal or triangular fuzzy numbers</i>
-----------------------	---

Description

Fuzzifies a variable modelled by trapezoidal or triangular fuzzy numbers

Usage

```
tr.gfuzz(data, breakpoints = 100)
```

Arguments

<code>data</code>	a matrix of 4 columns (p,q,r,s), where $p \leq q \leq r \leq s$. No NA are allowed.
<code>breakpoints</code>	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. breakpoints is fixed to 100 by default.

Value

A 3-dimensional array with dimensions (m,n,2), i.e. m lines, n columns, with no NA.

Examples

```
data <- matrix(c(1,1,2,2,3,3,4,4),ncol=4)
data.tr <- tr.gfuzz(data)
```

<code>wabl</code>	<i>Calculates a distance by the d_{wabl} between fuzzy numbers</i>
-------------------	---

Description

Calculates a distance by the d_{wabl} between fuzzy numbers

Usage

```
wabl(X, Y, i = 1, j = 1, theta = 1/3, breakpoints = 100)
```

Arguments

X	a fuzzy number.
Y	a fuzzy number.
i	parameter of the density function of the Beta distribution, fixed by default to $i = 1$.
j	parameter of the density function of the Beta distribution, fixed by default to $j = 1$.
theta	a numerical value between 0 and 1, representing a weighting parameter. By default, theta is fixed to $1/3$ referring to the Lebesgue space. This measure is used in the calculations of the following distances: d_Bertoluzza, d_mid/spr and d_phi-wabl/ldev/rdev.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.

Value

A numerical value.

Weighted.fuzzy.mean	<i>Calculates the weighted fuzzy sample mean</i>
---------------------	--

Description

Calculates the weighted fuzzy sample mean

Usage

```
Weighted.fuzzy.mean(
  data.fuzzified,
  weight,
  breakpoints = 100,
  alphacuts = FALSE
)
```

Arguments

data.fuzzified	a fuzzification matrix constructed by a call to the function FUZZ or the function GFUZZ, or a similar matrix. No NA are allowed.
weight	a weighting vector of the same length of the fuzzification matrix. No NA allowed.
breakpoints	a positive arbitrary integer representing the number of breaks chosen to build the numerical alpha-cuts. It is fixed to 100 by default.
alphacuts	fixed by default to "FALSE". No alpha-cuts are printed in this case.

Value

If the parameter `alphacuts="TRUE"`, the function returns a matrix composed by 2 vectors representing the numerical left and right alpha-cuts. For this output, `is.alphacuts = TRUE`. If the parameter `alphacuts="FALSE"`, the function returns a trapezoidal fuzzy number given by the quadruple (p,q,r,s) .

Examples

```
mat <- matrix(c(1,2,2,3,3,4,4,5), ncol =4)
w <- c(1,3)
Weighted.fuzzy.mean(mat, w)
```

Index

adjusted.weight.MI, [4](#)
adjusted.weight.SI, [5](#)

Bertoluzza, [6](#)
boot.mean.algo1, [7](#)
boot.mean.algo2, [8](#)
boot.mean.ml, [9](#)

cube, [10](#)

D2, [11](#)
Defuzz.FANOVA, [11](#)
Delta.pq, [12](#)
Delta_jki, [13](#)
distance, [14](#)
DSGD, [15](#)
DSGD.G, [16](#)

FANOVA, [16](#)
FANOVA.approximation, [18](#)
FANOVA.distance, [19](#)
FANOVA.exact, [20](#)
FANOVA.summary, [21](#)
fci.ml, [22](#)
fci.ml.boot, [23](#)
FMANOVA, [24](#)
FMANOVA.approximation, [26](#)
FMANOVA.distance, [27](#)
FMANOVA.exact, [28](#)
FMANOVA.interaction.summary, [29](#)
FMANOVA.summary, [30](#)
Ftests, [30](#)
FTukeyHSD, [31](#)
FUZZ, [32](#)
Fuzzy.CI.ML.test, [33](#)
Fuzzy.CI.test, [35](#)
Fuzzy.decisions, [37](#)
Fuzzy.decisions.ML, [38](#)
Fuzzy.Difference, [40](#)
Fuzzy.exact.variance, [41](#)
Fuzzy.exact.variance.poly.left, [42](#)
Fuzzy.exact.variance.poly.right, [42](#)
Fuzzy.p.value, [43](#)
Fuzzy.p.value.mean, [44](#)
fuzzy.predicted.values, [46](#)
fuzzy.residuals, [47](#)
Fuzzy.sample.mean, [47](#)
Fuzzy.sample.variance.approximation, [48](#)
Fuzzy.sample.variance.approximation1, [48](#)
Fuzzy.sample.variance.approximation2, [49](#)
Fuzzy.sample.variance.approximation3, [49](#)
Fuzzy.sample.variance.approximation4, [50](#)
Fuzzy.sample.variance.approximation5, [50](#)
Fuzzy.Square, [51](#)
Fuzzy.Square.poly.left, [51](#)
Fuzzy.Square.poly.right, [52](#)
Fuzzy.variance, [53](#)

GaussianBellFuzzyNumber, [54](#)
GaussianFuzzyNumber, [55](#)
GFUZZ, [56](#)
GLOB.EVAL, [57](#)
GLOB.EVAL.mean, [59](#)
GSGD, [61](#)

IND.EVAL, [62](#)
int.0, [64](#)
int.ct, [65](#)
int.simpson, [65](#)
int.t, [66](#)
integrate.num, [66](#)
is.alphacuts, [67](#)
is.balanced, [67](#)
is.fuzzification, [68](#)

is.trfuzzification, [68](#)

Kurtosis, [69](#)

Mid.Spr, [70](#)

Moment, [71](#)

n_jk., [73](#)

n_jkq., [73](#)

nbreakpoints, [72](#)

optimal.distance, [74](#)

p.value.fisher, [75](#)

p.value.log, [77](#)

p.value.mean.log, [78](#)

p.value.mean.normal, [80](#)

p.value.mean.poisson, [81](#)

p.value.mean.Student, [82](#)

p.value.normal, [84](#)

p.value.poisson, [85](#)

p.value.Student, [87](#)

prm_polygon, [88](#)

prm_trapezoid, [91](#)

prm_triangle, [92](#)

R, [92](#)

Rho1, [93](#)

Rho2, [94](#)

Rhop, [94](#)

Ri, [95](#)

Sample.variance, [96](#)

SEQ.ORDERING, [97](#)

SEQ.ORDERING.APPROXIMATION, [97](#)

SEQ.ORDERING.EXACT, [98](#)

SGD, [98](#)

Skewness, [99](#)

square, [100](#)

summary_prm, [100](#)

summary_prm_scores, [101](#)

tr.gfuzz, [102](#)

wabl, [102](#)

Weighted.fuzzy.mean, [103](#)